

IPCC Inventory Software

User Manual Version 2.88

Compiled by:

SPIRIT Inc., Bratislava, Slovak Republic, January 2013

Supervised by:

Technical Support Unit of the IPCC Task Force on National Greenhouse Gas Inventories

Revised:

September 2023 (Version 2.88)

Contents

1	BACKGROUND AND PURPOSE.....	- 4 -
2	GETTING STARTED WITH THE SOFTWARE.....	- 5 -
2.1	FIRST RUN	- 5 -
2.1.1	<i>Define Superuser</i>	- 5 -
2.1.2	<i>Choose country.....</i>	- 5 -
2.1.3	<i>Create Inventory Year.....</i>	- 5 -
2.2	CHECK AND MODIFY INVENTORY PREFERENCES	- 6 -
2.3	CHECK AND SET DEFAULT CO ₂ EQUIVALENTS.....	- 6 -
2.3.1	<i>Fixed CO₂ Equivalent types</i>	- 7 -
2.3.2	<i>Adding custom CO₂ Equivalent type.....</i>	- 7 -
2.3.3	<i>Deleting custom CO₂ Equivalent type.....</i>	- 7 -
2.3.4	<i>Setting default CO₂ Equivalent type</i>	- 7 -
2.4	DEFINE USERS	- 7 -
2.4.1	<i>List of Users</i>	- 8 -
2.4.2	<i>Selected User Details</i>	- 8 -
2.4.3	<i>Adding new user.....</i>	- 8 -
2.4.4	<i>Editing existing user</i>	- 9 -
2.4.5	<i>Deleting existing user</i>	- 9 -
2.4.6	<i>Resetting password of existing user</i>	- 9 -
2.5	DISTRIBUTE DATABASE	- 9 -
2.5.1	<i>Saving database</i>	- 9 -
2.5.2	<i>Share one database vs. maintaining multiple databases.....</i>	- 9 -
2.5.3	<i>Using the software in an inventory team</i>	- 9 -
3	WORKING WITH THE SOFTWARE	- 11 -
3.1	MAIN WINDOW.....	- 11 -
3.2	MAIN MENU STRUCTURE.....	- 11 -
3.2.1	<i>Application menu</i>	- 11 -
3.2.1.1	Preferences.....	- 11 -
3.2.1.2	Language.....	- 16 -
3.2.1.3	Exit	- 16 -
3.2.2	<i>Database menu</i>	- 16 -
3.2.2.1	Open/Close Database	- 16 -
3.2.2.2	Save as	- 17 -
3.2.2.3	Properties	- 17 -
3.2.2.4	Logout	- 18 -
3.2.3	<i>Inventory Year menu</i>	- 18 -
3.2.3.1	Choosing Inventory Year.....	- 18 -
3.2.3.2	Creating new Inventory Year	- 18 -
3.2.3.3	Efficient data entry using Inventory Year menu	- 18 -
3.2.4	<i>Worksheets menu.....</i>	- 19 -
3.2.5	<i>Reports menu</i>	- 19 -
3.2.5.1	Summary table.....	- 19 -
3.2.5.2	Short Summary table	- 19 -
3.2.5.3	Sectoral tables	- 19 -
3.2.5.4	Background tables	- 20 -
3.2.5.5	Reporting Table 7a – Uncertainties	- 20 -
3.2.6	<i>Tools</i>	- 20 -
3.2.6.1	Uncertainty Analysis	- 20 -
3.2.6.2	Reference Approach	- 21 -
3.2.6.3	Key Category Analysis	- 21 -
3.2.7	<i>Export/Import.....</i>	- 22 -
3.2.7.1	Export Worksheet Data	- 22 -
3.2.7.2	Export CO ₂ Equivalents	- 22 -
3.2.7.3	Export NAI Reporting Tables.....	- 23 -
3.2.7.4	Import Worksheet Data	- 23 -

3.2.7.5	Import CO ₂ Equivalents.....	- 24 -
3.2.7.6	UNFCCC CRT.....	- 24 -
3.2.8	<i>Administratate</i>	- 24 -
3.2.8.1	Users	- 24 -
3.2.8.2	CO ₂ Equivalents.....	- 24 -
3.2.8.3	Delete inventory	- 24 -
3.2.8.4	AFOLU Land Type Manager	- 25 -
3.2.8.5	AFOLU Land Representation Manager	- 26 -
3.2.8.6	AFOLU Livestock Manager	- 27 -
3.2.8.7	Guidelines Information Texts	- 30 -
3.2.9	<i>Window</i>	- 32 -
3.2.10	<i>Help</i>	- 32 -
4	WORKING WITH THE WORKSHEETS	- 33 -
4.1	BASIC LAYOUT OF THE WORKING AREA	- 33 -
4.2	WORKING WITH WINDOWS AND AREAS	- 33 -
4.2.1	<i>Undocking windows</i>	- 33 -
4.2.2	<i>Docking floating windows</i>	- 34 -
4.2.3	<i>Auto-hiding docking windows</i>	- 34 -
4.2.4	<i>IPCC 2006 Categories Navigation Window (tree)</i>	- 34 -
4.2.5	<i>IPCC 2006 Guidelines window</i>	- 35 -
4.2.6	<i>Worksheet notes window</i>	- 35 -
4.2.7	<i>User notes window</i>	- 35 -
4.2.8	<i>Time series window</i>	- 36 -
4.3	WORKING WITH THE GRID	- 36 -
4.3.1	<i>Row Status column</i>	- 37 -
4.3.2	<i>Adding new row</i>	- 37 -
4.3.3	<i>Canceling adding new row</i>	- 37 -
4.3.4	<i>Editing existing row</i>	- 37 -
4.3.5	<i>Canceling editing existing row / Undoing cell changes</i>	- 37 -
4.3.6	<i>Deleting rows</i>	- 38 -
4.3.7	<i>Value List cells</i>	- 38 -
4.3.8	<i>Notation Keys</i>	- 38 -
4.3.9	<i>Numeric values precision</i>	- 39 -
4.4	TIME SERIES DATA ENTRY.....	- 39 -
4.4.1	<i>Parameters</i>	- 39 -
4.4.2	<i>Row Identifiers</i>	- 39 -
4.4.3	<i>Export to Excel</i>	- 40 -
4.4.4	<i>Import from Excel</i>	- 40 -
4.4.5	<i>Copy and Paste functions</i>	- 40 -
4.4.6	<i>Chart</i>	- 41 -
5	EXAMPLE WORKSHEETS	- 42 -
5.1	FUEL COMBUSTION ACTIVITIES AND EMISSIONS	- 42 -
5.1.1	<i>Fuel Type</i>	- 42 -
5.1.2	<i>Uncertainties for Fuel Type</i>	- 43 -
6	UNFCCC CRT	- 44 -
6.1	INTRODUCTION	- 44 -
6.2	CRT DATA SET MANAGEMENT	- 44 -
6.2.1	<i>What is CRT Data Set</i>	- 44 -
6.2.2	<i>CRT Data Set management screen</i>	- 44 -
6.2.2.1	<i>New CRT Data Set</i>	- 44 -
6.2.2.2	<i>Edit CRT Data Set</i>	- 45 -
6.2.2.3	<i>Open tables</i>	- 46 -
6.2.2.4	<i>Generate JSON</i>	- 46 -
6.2.2.5	<i>Refresh values</i>	- 47 -
6.2.2.6	<i>Delete CRT Data Set</i>	- 48 -
6.3	CRT TABLES	- 48 -
6.3.1	<i>CRT Table actions</i>	- 49 -

6.3.1.1	Single-cell actions	- 49 -
6.3.1.2	Multi-cell actions	- 51 -
6.3.1.3	Editable cells	- 54 -
6.3.2	<i>CRT Table Documentation Box</i>	- 54 -
ANNEX 1		- 55 -

1 Background and Purpose

IPCC National Greenhouse Gas Inventories Programme and its Technical Support Unit located at IGES in Hayama, Japan, initiated the development of new GHG Inventory Software ("IPCC Inventory Software"). The purpose of this software is to implement Tier1, Tier2 and Tier 3 methodologies in the *2006 IPCC Guidelines* for National Greenhouse Gas Inventories for the preparation of national GHG inventories according to *2006 IPCC Guidelines* either for complete inventories or for separate categories or groups of categories. The primary target groups of users are inventory compilers who wish to apply default *2006 IPCC Guidelines* methods, trainers and trainees on national GHG inventory compilation, and Parties not included in Annex I of the Convention having limited resources without their own inventory systems.

The basic inventory data model looks like Figure 1.1




Figure 1.1 - Basic data relations

The basic approach of the software is to enable filling out the *2006 IPCC Guidelines* category worksheets with the activity and emission factor data. In addition it also supports many other functions related to database administration, Quality Control, data export / import as well as data reporting, as shown on the Figure 1.2.




Figure 1.2 - Basic software modules

2 Getting started with the software

The following chapters describe the steps necessary to initialize the software and the database. After performing these steps, the database is ready for distribution and sharing among inventory compilers participating in the national inventory, if desired, maintaining consistency among users.

2.1 First run

After installing the IPCC Inventory Software you are ready to launch the software for the first time. You will be asked to perform several mandatory actions described in the following sections to initialize the software and the database.

2.1.1 Define Superuser

It is necessary to define a **Superuser** that is responsible for defining additional users and has full control over the application and corresponding database (Figure 2.1).




Figure 2.1- Define Super User

2.1.2 Choose country

In this step it is necessary to choose desired **Region** and **Country/Territory** following Figure 2.2 below. Country is relevant for F-Gases, AFOLU and Waste worksheets. Selected country has no direct impact on other worksheets (Energy, IPPU). Please note that this country list is based on the UN list, which is available at <http://unstats.un.org/unsd/methods/m49/m49regin.htm>.




Figure 2.2 - Choose Country

2.1.3 Create Inventory Year

In this step it is necessary to create initial **Inventory Year** (Figure 2.3). After creating **Inventory Year**, software is successfully initialized and prepared for use or for additional tuning described in the next chapters.




Figure 2.3 – Creating Inventory Year

2.2 Check and modify Inventory Preferences

Use *Application / Preferences* menu to access Application preferences (Figure 2.4). Switch to *Inventory Year* tab as shown in the picture below.




Figure 2.4 – Setting Inventory Preferences

Check and modify following values, if necessary:

- 1) Use **Start inventory year** numeric box to set starting inventory year. Default is 1990.
- 2) Use **End inventory year** numeric box to set ending inventory year. Default is current year.
- 3) Use **Base Year for assessment of uncertainty in trend** numeric box to define Base Year for assessment of uncertainty in trend. Default is 1990.

If the start inventory year needs to be changed to earlier than 1990 (e.g. 1980), it is recommended to create new inventory for that year before starting working with the worksheets (menu *Inventory Year / Create New...*) or before distributing the database to other compilers.

After lowering start inventory year and creating new inventory for that year, you can delete default empty 1990 Inventory created in step 2.1.3 using *Administratate / Delete inventory* menu, if necessary.

2.3 Check and set default CO₂ Equivalents

Currently active (default) **CO₂ Equivalent Type** is indicated in the status bar located at the bottom of the main software window.

Use *Administratate / CO₂ Equivalents* menu to access management of CO₂ Equivalents.

CO2 Equivalents		
Type	SAR GWP (100 year time horizon)	Set as default
CO2, CH4 & N2O	Gas	CO2 Equivalent
	CARBON DIOXIDE (CO2)	1
	METHANE (CH4)	21
	NITROUS OXIDE (N2O)	310
Ethers and Halogenated Ethers	Gas	CO2 Equivalent
HFCs	HFC-23 (CHF3)	11700
	HFC-32 (CH2F2)	650
	HFC-41 (CH3F)	150
	HFC-43-10mee (CF3CHFCHFC2CF3)	1300
	HFC-125 (CHF2CF3)	2800

Figure 2.5 – CO₂ Equivalents

2.3.1 Fixed CO₂ Equivalent types

The **Type** list contains 4 fixed types with fixed CO₂ Equivalent values, that cannot be changed or deleted:

- SAR GWP – these are set as default
- TAR GWP
- AR4 GWP
- AR5 GWP

2.3.2 Adding custom CO₂ Equivalent type

To add custom CO₂ Equivalent type, follow the next steps:

- 1) Click **Add type...** button
- 2) Enter the unique name of the new type when asked and click **OK** - new custom CO₂ Equivalent type will appear within the **Type** list.
- 3) Use grid to go through all gases within all Gas groups and enter desired CO₂ Equivalent Values

2.3.3 Deleting custom CO₂ Equivalent type

To delete custom CO₂ Equivalent type, follow the next steps:

- 1) Use **Type** list to select custom CO₂ Equivalent type to be deleted
- 2) Click **Delete type** button and commit or cancel deletion when asked

2.3.4 Setting default CO₂ Equivalent type

To set the default CO₂ Equivalent type to be used for calculations within the whole software, follow the next steps:

- 1) Use **Type** list to select desired CO₂ Equivalent type
- 2) Click **Set as default** button to set it as default – new default CO₂ Equivalent type will be indicated in the status bar located at the bottom of the main software window.

2.4 Define users

Use *Administrare / Users* menu to access User Management system which is designated for adding new users and editing and deleting existing users in the currently open database.




Figure 2.6 – User Management

2.4.1 List of Users

This section contains the list of all users defined in the database divided into two groups:

- **Superusers** – contains the list of all Superusers. User marked blue represents currently logged in user. Following restrictions apply for Superusers:
 - Currently logged in user is prohibited to remove itself from the Superusers group for security reasons.
 - Currently logged in user is prohibited to delete itself
 - All worksheets are allowed automatically without possibility to change the list of allowed worksheets
- **Users** – contains the list of ordinary users. Following restrictions apply:
 - Access to Administrate section of the software is prohibited
 - Can see and edit only worksheets specified as *Allowed Worksheets*

2.4.2 Selected User Details

- **Login** – represents the login name. Login name must be unique within one particular database.
- **Superuser** – defines the user as a Superuser (if checked)
- **Allowed Worksheets** – defines the list of worksheets user can see and edit (applies to ordinary users only)

2.4.3 Adding new user

Take following steps to define new user:

- 1) Enter the desired unique login name into the **Login** textbox
- 2) Use **Superuser** checkbox to define user as a Superuser (checked) or ordinary user (unchecked)
- 3) In case of ordinary user define **Allowed Worksheets** for the user to work with
- 4) Click **Set password** button to explicitly set password for new user
- 5) Click **Add new** button to save new user into database

2.4.4 **Editing existing user**

Take following steps to edit existing user:

- 1) Click on the desired user within **List of users**
- 2) Change desired user details
- 3) Click **Save** button to save changes into database

2.4.5 **Deleting existing user**

Take following steps to delete existing user:

- 1) Click on the desired user within **List of users**
- 2) Click **Delete** button to delete user
- 3) Commit or cancel deletion when asked

2.4.6 **Resetting password of existing user**

Take following steps to reset existing user's password:

- 1) Click on the desired user within **List of users**
- 2) Click **Set password** to reset password to new one
- 3) Enter and confirm new password when asked

2.5 **Distribute database**

After performing all steps described in the previous chapters, the database is ready to be used or distributed to additional inventory compilers participating on national inventory, if necessary.

2.5.1 **Saving database**

Use *Database / Save As...* menu to save currently open database to a new file:

- 1) Select destination folder and file
- 2) Choose whether to remove password protection (see note below)
- 3) Decide whether to compress (ZIP) database file (compressed database file must be uncompressed (unzipped) before opening it in the software).

NOTE: Do not remove password protection. Removing the password protection will prevent the database from opening in the software (Software strictly accepts password protected database only for security reasons).

2.5.2 **Share one database vs. maintaining multiple databases**

Now you can decide how you would prefer the database to be distributed. There are the following possibilities:

- 1) Share database file on a network drive – copy your database file created in chapter 2.5.1 to some shared folder on the network, where other inventory compilers have read/write access. This alternative is strongly recommended, because after making administrative changes, all compilers are automatically affected.
- 2) Send a copy of database file created in chapter 2.5.1 to each of the inventory compilers (e.g. via e-mail). Administrative changes must be performed within each copy of the database to maintain consistency across inventory compilers. This approach can easily lead to inconsistency amongst compilers and therefore is not recommended.

2.5.3 **Using the software in an inventory team**

The safe and simple way to share the data between users is to share one database. The following steps, 2) through 4) should be performed iteratively. Figure 2.7 shows the data-flow in an inventory team.

- 1) The project manager should initialize the database as described in Chapter 2.1 – 2.4.
- 2) The project manager provides the database (ACCDB file) to each user.
- 3) After users update the data to their database, this data should be exported as XML file (see Chapter 3.2.7).
- 4) The manager imports the XML file to update the database.

This will reduce the chances of losing or overwriting the data unintentionally.




Figure 2.7 – Using the software in an inventory team

3 Working with the Software

3.1 Main window

Main window is a Multiple Document Interface window which acts as a container for all other software dialogs and windows.




Figure 3.1 – Main window

It consists of:

- Window title – Main software title followed by the login name of currently logged in user and optionally name of the currently active child window.
- Main menu (top) – for accessing all of the software functions / modules
- Working area (center) – place where all dialogs and child windows are displayed
- Status bar (bottom) – bar that contains useful information related to currently open database, currently chosen Inventory Year, etc.

3.2 Main menu structure

3.2.1 Application menu

3.2.1.1 Preferences

This opens dialog window that allows the user to adjust preferred working area settings, like appearance of dialogs, database related preferences and backup, default number of decimal places shown in worksheets and reports, range of inventory years and coloring and other properties of grids.

General




Figure 3.2 – General preferences

- **Start main application window maximized** – if checked, main application window size will be automatically scaled to fit the whole available screen after starting the software.
- **Prompt user on application exit** – if checked, user is always prompted whether to really exit application or not.
- **Show login dialog after logout** – if checked, new login dialog will appear automatically after currently logged in user logs out.
- **Show choose inventory year dialog after login** – if checked, user is prompted to choose inventory year to work with. If unchecked, previously used inventory year will be activated automatically.
- **Show informative message box after choosing Inventory Year** – if checked, user is informed of currently active inventory year after activating particular inventory year (activated automatically or by user action).

Database




Figure 3.3 – Database preferences

- **Open last used database at application startup** – if checked, previously database will be open automatically at startup; otherwise user will have to explicitly open the desired database.
- **Show login dialog after opening database** – if checked, login dialog will be displayed automatically after opening the database file; otherwise user will have to explicitly open login dialog via menu.
- **Show database properties dialog after opening database** – if checked, dialog containing currently open database details will be shown automatically after opening database file.
- **Show Open Database dialog after closing current database** – if checked, Open Database dialog will be automatically shown after closing current database.
- **Prompt before closing current database** – if checked, user will be asked to confirm the closing of the current database; otherwise the database will be closed without warning.
- **Prompt for backup if last backup older than N day(s)** – user is automatically asked to make a backup of the database if last backup is older than N day(s).
- **Always prompt for backup after opening database** – if checked, user is asked to make a backup of the database every time the database is open, no matter how old the last backup.

Worksheets




Figure 3.4 – Worksheet preferences

- **Open worksheets window after login** – if checked, window containing worksheets will be automatically open after user logs in; otherwise user will have to open worksheets window via menu.
- **Open worksheets window maximized** – if checked, worksheets window will automatically scale to fit main application window.
- **Expand full IPCC 2006 category structure by default** – if checked, tree containing 2006 IPCC hierarchy will be expanded automatically to show the whole hierarchy; otherwise only main sectors will be shown initially.
- **Automatically navigate to last visited IPCC 2006 Category** – if checked, last visited IPCC category will be automatically selected upon opening the Worksheet window.
- **Maximum numbers of decimal places** – defines maximum numbers of decimal places for numbers to be displayed in calculation sheets (worksheet grids).
- **Zero padding** – if checked all decimal numbers in grids will be zero-aligned.
E.g. 0.1 will become 0.10000 - padded with zeros up to the maximum number of decimal places – 5 in this case.

Reports




Figure 3.5 – Reports preferences

- **Default number of decimal places** – numbers in reports will be automatically rounded according to defined number of decimal places here.
- **Zero padding** – if checked all decimal numbers in grids will be zero-aligned. E.g. 0.1 will become 0.100 - padded with zeros up to the maximum number of decimal places – 3 in this case
- **Open report windows maximized** - if checked, reporting windows will automatically scale to fit main application window.

Inventory Year




Figure 3.6 – Inventory Year preferences

- **Start inventory year** – defines starting inventory year. Default is 1990.
- **End inventory year** – defines ending inventory year. Default is current year.
- **Base Year for assessment of uncertainty in trend** – defines base year used in Uncertainty Analysis. Default is 1990.

Grid




Figure 3.7 – Grid

- **Look preset** – provides the user with the set of standard predefined look presets to choose from
- **Header** - defines the look of the grid header
- **Selected row** – defines the look of the selected grid row
- **Computed cells** – defines the look of grid cells that are computed (calculated)
- **Use thousands separator** – if checked, thousand separator will be used to separate thousands in all numbers in grids. Thousands separator follows the operating system's Control Panel / Regional Settings.

3.2.1.2 Language

This allows the user to switch between different languages. Default language is English. Supplementary software called **Translation Editor** (which is included in setup) can be used to define other languages and translate texts.

3.2.1.3 Exit

Exits the software.

3.2.2 Database menu

3.2.2.1 Open/Close Database

If database is open, use this menu item to close the current database. Current logged- in user will be logged out automatically. All database related functions and modules of the software will become disabled.

If database is closed use this menu item to browse for and open new database. All database related functions will become available again after valid user logs in.

Automatic database upgrade

Starting from version 2.10 software supports automatic conversion of databases coming from the previous versions of the software (versions 2.00 and later are supported). This means users can comfortably use their existing databases from previous versions without putting any extra effort to transfer existing data. When database from older version of the software is open in new version of the software user will be prompted to start automatic database conversion. After database is successfully converted it will become fully compatible with the new version of the software.

3.2.2.2 Save as

This menu item allows the user to save database under a different file name to a different location. It is possible to compress (ZIP) saved database file to save space. This opens the possibility to maintain several independent versions of the database. Database is password protected, however it is possible to remove password protection during saving. **Database with password protection removed cannot be opened by the software.**

3.2.2.3 Properties

This menu item can be used to display dialog window containing properties of the currently open database.




Figure 3.8 – Database properties

Following information is available:

- **Database file** – full path to currently open database file (ACCDB)
- **Database version** – version of the database file
- **Database size** – size of the database file in bytes
- **Date created** – the date when the database was created
- **Date modified** – the date of the last modification of data in the database
- **Last backup** – the date of the last database backup
- **CO2 Equivalents** – currently selected GWP type. GWP types can be managed using the *Administrate / CO2 Equivalents* menu.
- **Inventory Years** – the list of inventory years in the currently open database
- **Users** – the list of defined users in the currently open database

Button **Compact & Repair** can be used to compact (to reduce size on disk) or repair the database file (in case it is corrupted).

3.2.2.4 Logout

This menu item logs out currently logged in user.

3.2.3 Inventory Year menu

This menu allows the user to choose current inventory year as well as to create new inventory year.

3.2.3.1 Choosing Inventory Year

Click *Choose...* menu item to display the following dialog box.




Figure 3.9 – Choose Inventory Year

After choosing the desired Inventory Year and pressing the OK button, all related software modules will update their current information and data corresponding to new Inventory Year.

3.2.3.2 Creating new Inventory Year

Click *Create new...* menu item to display the following dialog box.




Figure 3.10 – Create new Inventory Year

Take the following steps to create new Inventory Year:

- 1) Choose available Inventory Year from the **New Inventory Year** list. The list does not contain years that were already created and interval is from **Start inventory year** to **End inventory year** as defined in *Application / Preferences / Inventory year* tab.
- 2) Decide whether to create empty inventory year or copy of existing inventory year using the appropriate radio button.
- 3) In case of copy, choose the source inventory year from the corresponding list of available inventory years.
- 4) Click **Create** button to create new inventory year. After creating new year it will be automatically set as current Inventory Year.

3.2.3.3 Efficient data entry using Inventory Year menu

The efficient and optimal way to enter data is:

- 1) Complete inventory for one basic year at first
- 2) Create additional years by copying data (see 3.2.3.2) from existing year containing completed inventory which created in Step 1
- 3) Use **time series data entry** to make adjustments to data across years

3.2.4 Worksheets menu

This menu item opens the Worksheets window containing worksheets as defined in *2006 IPCC Guidelines*¹. See Chapter 3.3 for detailed information.

3.2.5 Reports menu

This menu item allows the user to calculate *2006 IPCC Guidelines* Reporting Tables. The reporting tables include the possibility to select number of decimal places of the emissions reported, the possibility to write and save text into documentation box of the report as well as function to export tables to Excel.

3.2.5.1 Summary table

This report displays all Greenhouse Gas emissions divided into *2006 IPCC Guidelines* Categories (up to level 3). The values are calculated from sectoral tables.

Categories	Emissions (Gg)			Emissions CO2 Equivalents (Gg)				Emissions (Gg)				
	Net CO2 (1)(2)	CH4	N2O	HFCs	PFCs	SF6	Other halogenated gases with CO2 equivalent conversion factors (3)	Other halogenated gases without CO2 equivalent conversion factors (4)	NOx	CO	NMVOCs	SO2
Total National Emissions and Removals	69927.972	1164.117	2.618	76124.414	204420.180	1034650.380	0.000	0.007	0.034	0.991	0.000	0.000
1 - Energy	54909.952	1507.496	58.274	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000
1.A - Fuel Combustion Activities	53217.218	12.049	2.214	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000
1.A.1 - Energy Industries	32955.271	0.479	0.481						0.000	0.000	0.000	0.000
1.A.2 - Manufacturing Industries and Construction	3516.442	1.203	0.160						0.000	0.000	0.000	0.000
1.A.3 - Transport	16745.506	10.367	1.573						0.000	0.000	0.000	0.000
1.A.4 - Other Sectors	0.000	0.000	0.000						0.000	0.000	0.000	0.000

Figure 3.11 – Example of Summary Table

3.2.5.2 Short Summary table

This reporting table displays all Greenhouse Gas emissions divided into *2006 IPCC Guidelines* Sub-sectors (up to level 2). The values are aggregated from Summary table.

Categories	Emissions (Gg)			Emissions CO2 Equivalents (Gg)				Emissions (Gg)				
	Net CO2 (1)(2)	CH4	N2O	HFCs	PFCs	SF6	Other halogenated gases with CO2 equivalent conversion factors (3)	Other halogenated gases without CO2 equivalent conversion factors (4)	NOx	CO	NMVOCs	SO2
Total National Emissions and Removals	69927.972	1164.117	2.618	76124.414	204420.180	1034650.380	0.000	0.007	0.034	0.991	0.000	0.000
1 - Energy	54909.952	1507.496	58.274	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000
1.A - Fuel Combustion Activities	53217.218	12.049	2.214						0.000	0.000	0.000	0.000
1.B - Fugitive emissions from fuels	1012.734	1495.447	56.060						0.000	0.000	0.000	0.000
1.C - Carbon dioxide Transport and Storage	680.000								0.000	0.000	0.000	0.000
2 - Industrial Processes and Product Use	2329.659	0.536	1390.625	76124.414	204420.180	1034650.380	0.000	0.007	0.000	0.000	0.000	0.000
2.A - Mineral Industry	7.809								0.000	0.000	0.000	0.000
2.B - Chemical Industry	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000

Figure 3.12 – Example of Short summary table

3.2.5.3 Sectoral tables

This set of reporting tables is available for each sector and displays Greenhouse Gas emissions divided into detailed *2006 IPCC Guidelines* categorization (up to the most disaggregated level). The values are taken from the Background tables. Energy sectoral table contains additional functionality regarding **Precursors (NOx, CO, NMVOCs, SO2)**. These can be manually edited here.

Categories	Emissions (Gg)						
	CO2	CH4	N2O	NOx	CO	NMVOCs	SO2
1 - Energy	54909.952	1507.496	58.274	0.000	0.000	0.000	0.000
1.A - Fuel Combustion Activities	53217.218	12.049	2.214	0.000	0.000	0.000	0.000
1.A.1 - Energy Industries	32955.271	0.479	0.481	0.000	0.000	0.000	0.000
1.A.1.a - Main Activity Electricity and Heat Production	30202.577	0.360	0.457	0.000	0.000	0.000	0.000
1.A.1.a.i - Electricity Generation	27273.761	0.329	0.410	0.000	0.000	0.000	0.000
1.A.1.a.ii - Combined Heat and Power Generation (CHP)	0.000	0.000	0.000	0.000	0.000	0.000	0.000
1.A.1.a.iii - Heat Plants	2928.816	0.031	0.046	0.000	0.000	0.000	0.000
1.A.1.b - Petroleum Refining	2752.694	0.119	0.024	0.000	0.000	0.000	0.000
1.A.1.c - Manufacture of Solid Fuels and Other Energy Industries	0.000	0.000	0.000	0.000	0.000	0.000	0.000
1.A.1.c.i - Manufacture of Solid Fuels	0.000	0.000	0.000	0.000	0.000	0.000	0.000

Figure 3.13 – Example of Energy Sectoral Table

¹ 2006 IPCC Guidelines for the National Greenhouse Gas Inventories

3.2.5.4 Background tables

This set of reporting tables displays activity rates, fuel types (if applicable) and Greenhouse Gas emissions divided into detailed 2006 *IPCC Guidelines* categorization (up to the most disaggregated level). The values are taken from the Worksheets. There is a special **Reporting Table 1.4b** for category **1.C CO₂ transport and storage** which is editable.

IPCC 2006 Categories		Activity (TJ)						Emissions Solid (Gg)			Emissions Liquid (Gg)			Emissions Gas (Gg)	
		Solid	Liquid	Gas	Other Fossil Fuels	Peat	Biomass	CO ₂	CH ₄	N ₂ O	CO ₂	CH ₄	N ₂ O	CO ₂	CH ₄
► 1.A - Fuel Combustion Activities		327586.000	310685.000	0.000	40100.000	0.000	94950.000	28573.002	0.295	0.444	21127.775	10.552	1.610	0.000	0.000
1.A.1 - Energy Industries		299386.000	615500.000	0.000	0.000	0.000	94950.000	28573.002	0.295	0.444	4382.269	0.185	0.037	0.000	0.000
1.A.1.a - Main Activity Electricity and Heat Production		299386.000	21850.000	0.000	0.000	0.000	94950.000	28573.002	0.295	0.444	1629.575	0.066	0.013	0.000	0.000
1.A.1.a.i - Electricity Generation		268426.000	21850.000	0.000	0.000	0.000	25644.186	0.264	0.397	1629.575	0.066	0.013	0.000	0.000	
1.A.1.a.ii - Combined Heat and Power Generation (CHP)		0.000	0.000	0.000	0.000	0.000	94950.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000
1.A.1.a.iii - Heat Plants		30960.000	0.000	0.000	0.000	0.000	2928.816	0.031	0.046	0.000	0.000	0.000	0.000	0.000	0.000
1.A.1.b - Petroleum Refining		0.000	39700.000	0.000	0.000	0.000	0.000	0.000	0.000	2752.694	0.119	0.024	0.000	0.000	0.000

Figure 3.14 – Example of Energy Background Table 1.1

3.2.5.5 Reporting Table 7a – Uncertainties

This Reporting Table is an aggregated version of Uncertainty Analysis Table 3.2. The list of aggregated categories is based on Table 4.1 of Volume 1, Chapter 4 of *2006 IPCC Guidelines*. Uncertainties from disaggregated levels are combined by multiplication according to Equation 3.1 of Volume 1, Chapter 3 of *2006 IPCC Guidelines*.

Reporting Table 7a - Uncertainties											Contribution to Variance by Category in Year T			Inventory limit in national emissions for year t increase with respect to base year (% of base year)	Uncertainty
Base Year	1990	Year T	1994												
IPCC 2006 Categories	Gas			Base Year emissions or removals (Gg CO ₂ equivalent)	Year T emissions or removals (Gg CO ₂ equivalent)	Activity Data Uncertainty (%)	Emission Factor Uncertainty (%)	Combined Uncertainty (%)	Contribution to Variance by Category in Year T						
► 1 - Energy															
1.A.1 - Energy Industries - Liquid Fuels	CO ₂			4382.269	3387.944	7.071	8.678	11.194	0.000	0.000	77.310				
	CH ₄			3.078	3.021	7.071	323.555	323.632	0.000	0.000	77.904				
	N ₂ O			11.448	8.919	7.071	323.555	323.632	0.000	0.000	77.904				
1.A.1 - Energy Industries - Solid Fuels	CH ₄			6.192	6.468	7.071	200.062	200.187	0.000	0.000	104.468				
	N ₂ O			137.541	157.296	7.071	222.278	222.391	0.000	0.000	114.363				
1.A.1 - Energy Industries - Biomass	CH ₄			197.889	0.000	5.000	5.000	7.071	0.000	0.000	0.000	0.000			
	N ₂ O			80.743	0.000	5.000	5.000	7.071	0.000	0.000	0.000	0.000			
1.A.1 - Energy Industries - Solid Fuels	CO ₂			2928.816	0.000	5.000	5.000	7.071	0.000	0.000	0.000	0.000			

Figure 3.15 – Example of Reporting Table 7a - Uncertainties

3.2.6 Tools

3.2.6.1 Uncertainty Analysis

This menu item allows creating uncertainty Reporting Table 3.2 as defined in the *2006 IPCC Guidelines*. The values are entered in each Worksheet. User should enter uncertainty values for every activity and Emission Factor. Default uncertainty values are applied when the user does not enter any uncertainty values.

There is no limit and no check for uncertainty range, i.e. it is the responsibility of the user to define the appropriate values. Default uncertainty values presented in the *2006 IPCC Guidelines* for almost all the default EFs and AD are preloaded as default upper and lower limits.

The procedure of calculation uncertainty in Table 3.2 is explained on page 3.29 of Chapter 3 in Volume 1 of the *2006 IPCC Guidelines*. More information on how to enter Uncertainties within each type of worksheet can be found in Chapter 3.3 of this document.

To perform Uncertainty Analysis, click the **Refresh Data** button.

Uncertainty Analysis - Approach 1 (Table 3.2)							
Base year for assessment of uncertainty in trend		1990	Year T	1994			
IPCC 2006 Categories		Gas	Base Year emissions or removals (Gg CO ₂ equivalent)	Year T emissions or removals (Gg CO ₂ equivalent)	Activity Data Uncertainty (%)	Emission Factor Uncertainty (%)	Combined Uncertainty (%)
► 1.A - Fuel Combustion Activities							
1.A.1.a - Electricity Generation - Liquid Fuels		CO ₂	1193.979	635.250	5.000	6.136	7.915
		CH ₄	1.461	0.520	5.000	228.788	228.843
		N ₂ O	4.314	1.535	5.000	228.788	228.843
1.A.1.a.i - Electricity Generation - Solid Fuels		CO ₂	18345.840	29743.850	5.000	12.412	13.381
		CH ₄	3.891	6.468	5.000	200.000	200.062
		N ₂ O	88.937	157.296	5.000	222.222	222.278

Figure 3.16 – Example of Ucertainty Analysis table

3.2.6.2 Reference Approach

The Reference Approach is a top-down approach, using a country's energy supply data to calculate the emissions of CO₂ from combustion of mainly fossil fuels. The Reference Approach is a straightforward method that can be applied on the basis of relatively easily available energy supply statistics.




Figure 3.17 – Example of Reference Approach table

3.2.6.3 Key Category Analysis

It is *good practice* for each country to identify its national *key categories* in a systematic and objective manner, by performing a quantitative analysis of the relationships between the level and the trend of each category's emissions and removals and total national emissions and removals. Two Approaches for performing the key category analysis have been developed. Both Approaches identify *key categories* in terms of their contribution to the absolute level of national emissions and removals and to the trend of emissions and removals. The methods are described in Chapter 4.3, Volume 1 of 2006 *IPCC Guidelines*. To perform Key Category Analysis, click the **Refresh Data** button.




Figure 3.18 – Key Category Analysis

3.2.7 Export/Import

3.2.7.1 Export Worksheet Data

This menu item opens dialog box that allows selecting and exporting part of the current inventory year, i.e. one or more sectors, sub-sectors or categories into an XML file.




Figure 3.19 – Exporting worksheet data

Take the following steps to export part of an inventory year:

- 1) Select one or more category of interest. Categories containing worksheets (data) are marked blue.
- 2) Click the **Export** button and supply the destination XML file when asked.

3.2.7.2 Export CO₂ Equivalents

This menu item opens dialog box that allows exporting of custom (not fixed) CO₂ Equivalents into an XML file. The structure of hierarchy is: *Custom CO₂ Equivalent Type / Gas groups / Gases*.




Figure 3.20 – Exporting custom CO₂ Equivalents

Take the following steps to export custom CO₂ Equivalents:

- 1) Select the desired Custom GWP type of interest or just the particular Gases within gas groups.
- 2) Click the **Export** button and supply the destination XML file when asked.

3.2.7.3 Export NAI Reporting Tables

This menu item opens the window that allows calculating and exporting of the national communication table for Parties not included in Annex I to the Convention. Annex 1 to this user manual contains the details on mapping of the emission estimations based on 2006 IPCC Guidelines to the NAI reporting tables in the software.

Greenhouse gas source and sink categories	CO ₂ Emissions (Gg)	CO ₂ Removals (Gg)	CH ₄ (Gg)	N ₂ O (Gg)	CO (Gg)	NO _x (Gg)	NMVOCs (Gg)	SO _x (Gg)
Total National Emissions and Removals	69927.972	1164.117	2.618	0.991	0.034	0.000	0.000	0.000
1 - Energy	54909.952	1507.496	58.274	0.000	0.000	0.000	0.000	0.000
1A - Fuel Combustion Activities	53217.218	12.049	2.214	0.000	0.000	0.000	0.000	0.000
1A1 - Energy Industries	32955.271	0.479	0.481	0.000	0.000	0.000	0.000	0.000
1A2 - Manufacturing Industries and Construction (ISIC)	3516.442	1.203	0.160	0.000	0.000	0.000	0.000	0.000
1A3 - Transport	16745.506	10.367	1.573	0.000	0.000	0.000	0.000	0.000
1A4 - Other Sectors	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000
1A5 - Other	0.000	0.000	0.000	0.000	0.000	0.000	0.000	0.000

Figure 3.21 – Example of NAI Reporting Table

3.2.7.4 Import Worksheet Data

This menu item opens the dialog window that allows importing an XML file containing a part of an inventory, i.e. one or more sectors, sub-sectors or categories into the currently open database and currently chosen Inventory Year.




Figure 3.22 – Importing Worksheet Data

Take the following steps to import worksheet data:

- 1) Click the **Open** button to browse for XML file to be imported.
- 2) Check the details such as **XML Import Version**, **Source inventory year**, **Number of records** and decide whether this import file suits your needs.
- 3) Section **Categories to import** contains the list of all categories included in the source XML file. Select the categories of interest to be imported. All categories are selected by default.
- 4) Click the **Import** button to begin import. Progress bar will be shown to indicate the progress of import.

TIP: Button **View XML file** can be used to display the contents of the source XML file in Internet browser.

3.2.7.5 Import CO₂ Equivalents

This menu item opens the dialog window that allows importing of custom CO₂ Equivalents from an XML file.




Figure 3.23 – Importing custom CO₂ Equivalents

Take the following steps to import custom CO₂ Equivalents:

- 1) Click the **Open** button to browse for XML file to be imported.
- 2) Section **GWP Types to import** contains the list of all custom GWP types included in the source XML file. Select the custom GWP type of interest or just particular gases of interest to be imported.
- 3) Click the **Import** button to begin import. Progress bar will be shown to indicate the progress of import.

TIP: Button **View XML file** can be used to display the contents of the source XML file in Internet browser.

3.2.7.6 UNFCCC CRT

Refer to chapter [6 - UNFCCC CRT](#) for detailed information.

3.2.8 Administrate

Functions in this menu section are available to administrators (Superusers) only.

3.2.8.1 Users

This menu item opens dialog window that allows managing login names, passwords and rights to work with particular worksheets. See [Chapter 2.4](#) for detailed information.

3.2.8.2 CO₂ Equivalents

This menu item opens the dialog window that allows the administrator to manage CO₂ Equivalents. Except for predefined SAR, TAR and AR4 Equivalents, it is possible to define custom types. Default type of CO₂ Equivalents currently selected is indicated in the status bar and also in *Database Properties* dialog box. See [Chapter 2.3](#) for detailed information.

3.2.8.3 Delete inventory

This menu item opens the dialog window that allows deleting existing inventories. **USE THIS FUNCTION WITH CAUTION!**




Figure 3.24 – Deleting inventory

3.2.8.4 AFOLU Land Type Manager

This menu item opens a dialog window which allows managing Land Use Subcategories under AFOLU category 3.B – Land. This window is also accessible from relevant worksheets. Parameters defined here are used in all relevant worksheets.




Figure 3.25 – Land Type Manager

Land Type Manager window consists of the following sections:

- **Navigation section** – contains the list of Land Use Subcategories divided into corresponding main Land Type categories (Forest, Cropland, ...). Activation of the particular Land Use Subcategory shows relevant details.
- **Common Land Type Data** – contains data that is common for all Land Types (Country, Climate Region, ...)

- **Particular Land Use Subcategory data** – contains details of the particular Land Use Subcategory that is selected in the navigation section.

Adding new Land Use Subcategory

Take the following steps to define new Land Use Subcategory:

- 1) Select one of the main Land Use Categories in the Navigation section.
- 2) Click the **Add** button located at the bottom of the navigation section. New Land Use Subcategory will be created with the default name.
- 3) Enter desired details of the new Land Use Subcategory
- 4) Click the **Save** button to save new Land Use Subcategory into database

Editing existing Land Use Subcategory

Take the following steps to edit existing Land Use Subcategory:

- 1) Select the Land Use Subcategory of interest in the navigation section
- 2) Edit data as desired
- 3) Click the **Save** button to save changes into database or click the **Undo** button to discard all changes.

Making copy of existing Land Use Subcategory

It is possible to make a copy of existing Land Use Subcategory. Follow the next steps:

- 1) Select the Land Use Subcategory of interest in the navigation section
- 2) Click the **Copy** button located at the bottom of the navigation section.
- 3) New copy of selected Land Use Subcategory will be created with the new name
- 4) Edit data as desired
- 5) Click the **Save** button to save new Land Use Subcategory into database.

Deleting existing Land Use Subcategory

- 1) Select the Land Use Subcategory of interest in the navigation section
- 2) Click the **Delete** button located at the bottom of the navigation section
- 3) Confirm or cancel deletion when prompted

3.2.8.5 AFOLU Land Representation Manager

This menu item opens a dialog window which allows managing Land Representation for AFOLU categories under 3.B – Land. This window is also accessible from relevant worksheets. Parameters defined here are used in all relevant worksheets.

Figure 3.26 – Land Representation Manager

3.2.8.6 AFOLU Livestock Manager

This menu item opens a dialog window which allows managing Livestock for AFOLU category 3.A – Livestock. This window is also accessible from relevant worksheets under category 3.A – Livestock. Livestock manager is divided into several tabs. Parameters defined here are used in all relevant worksheets.

Geographical zones

Geographical zone	Average annual temperature [°C]	Remark
Sub-equitorial	≥ 28	
*		

Figure 3.27 – Geographical zones

This tab allows defining geographical zones and thus dividing country into smaller parts which differ by average temperature.

- **Adding new Geographical zone**
 - 1) Use last (add template) row to define new Geographical zone. Enter zone name, average temperature and optionally remark. Repeat to add more zones.
 - 2) Click the **Save** button to save new zones into database
- **Editing existing Geographical zone**
 - 1) Click on the existing Geographical zone
 - 2) Edit name, average temperature, remark. Repeat for other existing zones as necessary.
 - 3) Click the **Save** button to save changes into database; or click the **Undo** button to discard all changes.
- **Deleting existing Geographical zone**
 - 1) Click on the existing Geographical zone
 - 2) Click the iconic delete button located in the last cell of active row. Repeat for other zones if necessary.
 - 3) Click the **Save** button to commit delete operation into database or click **Undo** to undelete all zones marked for deletion.

Livestock




Figure 3.28 – Livestock Subcategories

This tab allows defining custom livestock subcategories and subdivisions under each 2006 IPCC Guidelines main Livestock categories or under additional user-defined “Other” Livestock categories.

- **Adding new user-defined “Other” Livestock Category**
 - 1) Use last (add template) row of top-level band to define new Livestock Category. Enter Livestock Category name. Repeat to add more categories.
 - 2) Click the **Save** button to save new categories into database
- **Editing existing user-defined “Other” Livestock Category**
 - 1) Click on the existing Livestock Category of interest.
 - 2) Edit name. Repeat for other Livestock Categories as desired.
 - 3) Click the **Save** button to save changes into database; or click the **Undo** button to discard all changes.
- **Deleting existing user-defined “Other” Livestock Category**
 - 1) Click on the existing Livestock Category of interest.
 - 2) Click the iconic delete button located in the last cell of active row. Repeat for other categories if necessary.
 - 3) Click the **Save** button to commit delete operation into database or click **Undo** to undelete all categories marked for deletion.
- **Adding new Livestock Subcategory**
 - 1) Expand the desired main Livestock Category (or user-defined “Other” category)
 - 2) Use last (add template) row to add new Livestock Subcategory. Enter Livestock Subcategory name. Repeat for other main categories as desired.
 - 3) Click the **Save** button to save new defined Livestock Subcategories into database
- **Editing existing Livestock Subcategory**
 - 4) Click on the existing Livestock Subcategory under main Livestock Category (or user-defined “Other” category) of interest.
 - 5) Edit name. Repeat for other Livestock Subcategories as desired.
 - 6) Click the **Save** button to save changes into database; or click the **Undo** button to discard all changes.
- **Deleting existing Livestock Subcategory**
 - 1) Click on the existing Livestock Subcategory under main Category (or user-defined “Other” category) of interest.

- 2) Click the iconic delete button located in the last cell of active row. Repeat for other subcategories if necessary.
- 3) Click the **Save** button to commit delete operation into database or click **Undo** to undelete all subcategories marked for deletion.

- **Adding new Livestock Subdivision**
 - 4) Expand the desired Livestock Subcategory
 - 5) Use last (add template) row to add new Livestock Subdivision. Enter Livestock Subdivision name. Repeat for other subcategories as desired.
 - 6) Click the **Save** button to save new defined Livestock Subdivisions into database
- **Editing existing Livestock Subdivision**
 - 7) Click on the existing Livestock Subdivision under Livestock Subcategory of interest.
 - 8) Edit name. Repeat for other Livestock Subdivisions as desired.
 - 9) Click the **Save** button to save changes into database; or click the **Undo** button to discard all changes.
- **Deleting existing Livestock Subdivision**
 - 1) Click on the existing Livestock Subdivision under Subcategory of interest.
 - 2) Click the iconic delete button located in the last cell of active row. Repeat for other subdivisions if necessary.
 - 3) Click the **Save** button to commit delete operation into database or click **Undo** to undelete all subdivisions marked for deletion.

Manure Management System

Livestock Manager																										
		Geographical zones	Livestock	Manure Management System																						
		<input type="button" value="Save"/> <input type="button" value="Undo"/> <input type="button" value="Close"/>																								
		<table border="1"> <thead> <tr> <th>System</th> <th>Definition</th> </tr> </thead> <tbody> <tr> <td><input checked="" type="checkbox"/> Pasture/Range/Paddock</td><td>The manure from pasture and range grazing animals is allowed to lie as deposited, and is not managed.</td></tr> <tr> <td><input type="checkbox"/> Daily spread</td><td>Manure is routinely removed from a confinement facility and is applied to cropland or pasture within 24 hours of excretion.</td></tr> <tr> <td><input checked="" type="checkbox"/> Solid storage</td><td>The storage of manure, typically for a period of several months, in unconfined piles or stacks. Manure is able to be stacked due to the presence of a sufficient amount of bedding material or loss of moisture by evaporation.</td></tr> <tr> <td><input type="checkbox"/> Dry lot</td><td>A paved or unpaved open confinement area without any significant vegetative cover where accumulating manure may be removed periodically.</td></tr> <tr> <td><input checked="" type="checkbox"/> Liquid/Slurry</td><td>Manure is stored as excreted or with some minimal addition of water in either tanks or earthen ponds outside the animal housing, usually for periods less than one year.</td></tr> <tr> <td><input type="checkbox"/> Uncovered anaerobic lagoon</td><td>A type of liquid storage system designed and operated to combine waste stabilization and storage. Lagoon supernatant is usually used to remove manure from the associated confinement facilities to the lagoon. Anaerobic lagoons are designed with varying lengths of storage (up to a year or greater), depending on the climate region, the volatile solids loading rate, and other operational factors. The water from the lagoon may be recycled as flush water or used to irrigate and fertilise fields.</td></tr> <tr> <td><input type="checkbox"/> Pit storage below animal confinements</td><td>Collection and storage of manure usually with little or no added water typically below a slatted floor in an enclosed animal confinement facility, usually for periods less than one year.</td></tr> <tr> <td><input type="checkbox"/> Anaerobic digester</td><td>Animal excreta with or without straw are collected and anaerobically digested in a large containment vessel or covered lagoon. Digesters are designed and operated for waste stabilization by the microbial reduction of complex organic compounds to CO₂ and CH₄, which is captured and flared or used as a fuel.</td></tr> <tr> <td><input type="checkbox"/> Burned for fuel</td><td>The dung and urine are excreted on fields. The sun dried dung cakes are burned for fuel.</td></tr> <tr> <td><input type="checkbox"/> Cattle and Swine deep bedding</td><td>As manure accumulates, bedding is continually added to absorb moisture over a production cycle and possibly for as long as 6 to 12 months. This manure</td></tr> </tbody> </table>			System	Definition	<input checked="" type="checkbox"/> Pasture/Range/Paddock	The manure from pasture and range grazing animals is allowed to lie as deposited, and is not managed.	<input type="checkbox"/> Daily spread	Manure is routinely removed from a confinement facility and is applied to cropland or pasture within 24 hours of excretion.	<input checked="" type="checkbox"/> Solid storage	The storage of manure, typically for a period of several months, in unconfined piles or stacks. Manure is able to be stacked due to the presence of a sufficient amount of bedding material or loss of moisture by evaporation.	<input type="checkbox"/> Dry lot	A paved or unpaved open confinement area without any significant vegetative cover where accumulating manure may be removed periodically.	<input checked="" type="checkbox"/> Liquid/Slurry	Manure is stored as excreted or with some minimal addition of water in either tanks or earthen ponds outside the animal housing, usually for periods less than one year.	<input type="checkbox"/> Uncovered anaerobic lagoon	A type of liquid storage system designed and operated to combine waste stabilization and storage. Lagoon supernatant is usually used to remove manure from the associated confinement facilities to the lagoon. Anaerobic lagoons are designed with varying lengths of storage (up to a year or greater), depending on the climate region, the volatile solids loading rate, and other operational factors. The water from the lagoon may be recycled as flush water or used to irrigate and fertilise fields.	<input type="checkbox"/> Pit storage below animal confinements	Collection and storage of manure usually with little or no added water typically below a slatted floor in an enclosed animal confinement facility, usually for periods less than one year.	<input type="checkbox"/> Anaerobic digester	Animal excreta with or without straw are collected and anaerobically digested in a large containment vessel or covered lagoon. Digesters are designed and operated for waste stabilization by the microbial reduction of complex organic compounds to CO ₂ and CH ₄ , which is captured and flared or used as a fuel.	<input type="checkbox"/> Burned for fuel	The dung and urine are excreted on fields. The sun dried dung cakes are burned for fuel.	<input type="checkbox"/> Cattle and Swine deep bedding	As manure accumulates, bedding is continually added to absorb moisture over a production cycle and possibly for as long as 6 to 12 months. This manure
System	Definition																									
<input checked="" type="checkbox"/> Pasture/Range/Paddock	The manure from pasture and range grazing animals is allowed to lie as deposited, and is not managed.																									
<input type="checkbox"/> Daily spread	Manure is routinely removed from a confinement facility and is applied to cropland or pasture within 24 hours of excretion.																									
<input checked="" type="checkbox"/> Solid storage	The storage of manure, typically for a period of several months, in unconfined piles or stacks. Manure is able to be stacked due to the presence of a sufficient amount of bedding material or loss of moisture by evaporation.																									
<input type="checkbox"/> Dry lot	A paved or unpaved open confinement area without any significant vegetative cover where accumulating manure may be removed periodically.																									
<input checked="" type="checkbox"/> Liquid/Slurry	Manure is stored as excreted or with some minimal addition of water in either tanks or earthen ponds outside the animal housing, usually for periods less than one year.																									
<input type="checkbox"/> Uncovered anaerobic lagoon	A type of liquid storage system designed and operated to combine waste stabilization and storage. Lagoon supernatant is usually used to remove manure from the associated confinement facilities to the lagoon. Anaerobic lagoons are designed with varying lengths of storage (up to a year or greater), depending on the climate region, the volatile solids loading rate, and other operational factors. The water from the lagoon may be recycled as flush water or used to irrigate and fertilise fields.																									
<input type="checkbox"/> Pit storage below animal confinements	Collection and storage of manure usually with little or no added water typically below a slatted floor in an enclosed animal confinement facility, usually for periods less than one year.																									
<input type="checkbox"/> Anaerobic digester	Animal excreta with or without straw are collected and anaerobically digested in a large containment vessel or covered lagoon. Digesters are designed and operated for waste stabilization by the microbial reduction of complex organic compounds to CO ₂ and CH ₄ , which is captured and flared or used as a fuel.																									
<input type="checkbox"/> Burned for fuel	The dung and urine are excreted on fields. The sun dried dung cakes are burned for fuel.																									
<input type="checkbox"/> Cattle and Swine deep bedding	As manure accumulates, bedding is continually added to absorb moisture over a production cycle and possibly for as long as 6 to 12 months. This manure																									
		<p>Only those Manure Management Systems that are selected here will appear in the worksheets</p>																								

Figure 3.29 – Manure Management Systems


This tab allows choosing manure management systems to be used in computation of N₂O emissions from Manure Management Systems. The list contains the predefined set of default Manure Management Systems as defined in the *2006 IPCC Guidelines*. Additionally it allows the user to define user-defined Manure Management Systems.

- **Choosing the Manure Management Systems**
 - 1) Use left column containing checkboxes to mark all desired Manure Management Systems that are relevant for your case and that will be used for computation of N₂O emissions from Manure Management Systems
 - 2) Chosen Manure Management Systems are highlighted green for better visual feedback

- **Adding new user-defined Manure Management System**
 - 1) Use last (add template) row to add new user-defined Manure Management System. Enter System and optionally Definition. Repeat for other user-defined Manure Management Systems as desired.
 - 2) Click the **Save** button to save new defined user-defined Manure Management Systems into database
- **Editing existing user-defined Manure Management System**
 - 1) Click on the existing user-defined Manure Management System.
 - 2) Edit System and Definition as desired. Repeat for other user-defined Manure Management Systems as desired.
 - 3) Click the **Save** button to save changes into database; or click the **Undo** button to discard all changes.

Only user-defined Manure Management Systems can be modified

- **Deleting existing user-defined Manure Management System**
 - 1) Click on the existing user-defined Manure Management System.
 - 2) Click the iconic delete button located in the last cell of active row. Repeat for other user-defined Manure Management Systems if necessary.
 - 3) Click the **Save** button to commit delete operation into database or click **Undo** to undelete all user-defined Manure Management Systems marked for deletion.



Only user-defined Manure Management Systems can be deleted

3.2.8.7 Guidelines Information Texts

This menu item opens a special dialog where rich-text can be edited for each of the *2006 IPCC Guidelines* Categories. Such texts will then be displayed for currently active *2006 IPCC Guidelines* Category in the “*IPCC 2006 Guidelines Window*” within Worksheets window.




Figure 3.30 – Guidelines Information Texts

Editing text for particular Category

- 1) Use „IPCC 2006 Categories“ navigation window to select desired IPCC 2006 Category. Text mapped to this category will be displayed in the large text area on the right
- 2) Click **Edit** button to open rich-text editor and edit text as necessary. Use formatting options (font, color, ...) of rich-text editor as desired




Figure 3.31 – Rich-text editor

- 3) Click **OK** to save changes or **Cancel** to discard all changes. In both cases the editor will close itself automatically.

Defined texts will be automatically displayed in the “IPCC 2006 Guidelines Window” for IPCC 2006 Category that is currently activated in the IPCC 2006 Categories navigation tree.

1) Limestone and other carbonate materials also are consumed in a variety of other industries not covered in Chapter 2 of Volume 3. Examples include carbonates used as fluxes and slagging agents in metals smelting and refining (e.g., iron and steel production and base metals such as copper), and as inputs to the chemical industry (e.g., fertiliser). The methods outlined here for estimating emissions from the use of carbonates are applicable to these other industries as well. It is good practice to allocate emissions from the use of limestone, dolomite and other carbonates to the industrial source category where they are emitted (e.g., iron and steel production).

2) 2.A.4.d should contain estimates of emissions that do not fit into any of the major

Country: Slovakia | Inventory Year: 1990 | Base year for assessment of uncertainty in trend: 1990 | CO2 Equivalents: SAR GWP (100 year time horizon) | Database file:

Figure 3.32 – Example of IPCC 2006 Guidelines Window content

3.2.9 Window

Use this menu to:

- **Minimize all** – minimizes all windows to display main working area.
- **Close all** – closes all open windows
- **Windows list** – quickly activate the particular window by selecting it from the window list

3.2.10 Help

User manual - this file

About - Important information about the Version of IPCC Inventory Software installed.




Figure 3.33 – About Box

4 Working with the Worksheets

4.1 Basic layout of the working area




Figure 4.1 - Basic layout of the screen

- **Navigation window** top - left enabling browsing the IPCC 2006 Category structure
- **Worksheet grid area** top - right enabling editing the activity and emission factor data
- **IPCC 2006 Guidelines area** bottom - left providing current information from the *Guidelines*
- **Worksheet notes** area below grid containing notes/guidance related to currently open worksheet
- **User notes** area bottom - middle enabling to edit and save user remarks related to currently open worksheet
- **Time Series chart** area bottom - right displaying CO₂ equivalent time series for selected category

4.2 Working with windows and areas

Windows containing top bar with "pin" and "down-arrow" icons are dockable windows. It is possible to reorder such windows and completely change the layout of the screen to suit users' needs or preferences. In the next chapters, information on how to use dockable windows is provided.

4.2.1 Undocking windows

Dockable windows can be undocked. Undocked window is called "floating window". Floating window can be placed anywhere within the screen and it always stays on top of other forms within the application. There are several ways to make docked window floating:

1. Double-clicking the top bar of the dockable window
2. Holding the left mouse button down over top bar and moving it to the desired location
3. Clicking on down-arrow icon in the top bar displays the menu containing "Floating" menu item. Clicking this item undocks window. (Figure 4.2)




Figure 4.2 - Dockable window menu

HINT: Double-click on the top bar of floating window docks the window to the place where it was docked previously.

4.2.2 Docking floating windows

While dragging the floating window, docking indicators appear within each docking area guiding the user to choose where to dock the window. It is necessary to place mouse cursor over one of the arrows within docking indicator. The box then will be displayed to show the user where the window being dragged will be placed after releasing the mouse.




Figure 4.3 - Docking the floating window

4.2.3 Auto-hiding docking windows

Docking windows can be switched to auto-hide mode using the "pin" icon located in top bar. This is useful if there is a need for more space for main working area. Windows switched to auto-hide mode hide themselves when inactive.

HINT: Placing the mouse cursor over "strip" containing the name of the hidden window automatically scrolls window into view.

Clicking the "pin" icon of auto-hidden window switches the auto-hide mode off.

4.2.4 IPCC 2006 Categories Navigation Window (tree)

This window contains full 2006 IPCC Guidelines Category tree structure (Figure 4.4). The navigation tree is useful to select the worksheet to work with. Worksheets are available within IPCC categories marked blue. The worksheet relevant to selected IPCC Category will be displayed in the main working area on the right. If there are more worksheets available within selected IPCC Category, they are organized in the "tabbed" working area where each tab represents the particular worksheet.

Clicking on the "Sector/ Sub-sector" level of the tree which is marked with gray color, will show the CO₂ equivalent time series graph of the "Sector/ Sub-sector".




Figure 4.4 - IPCC 2006 Category tree

4.2.5 IPCC 2006 Guidelines window

This window contains the information relevant to currently selected IPCC 2006 Category. Such information can be defined using “*Guidelines Information Texts*” dialog accessible from Administrate menu ([Chapter 3.2.8.6](#))




Figure 4.5 - IPCC 2006 Guidelines window

4.2.6 Worksheet notes window

This window contains additional information/guidance related to currently open worksheet.




Figure 4.6 – Worksheet notes

4.2.7 User notes window

This window can be used to enter additional textual information or reference for the selected worksheet within currently chosen inventory year.




Figure 4.7 – User notes

4.2.8 Time series window

This window contains the chart with emission time series across all inventory years for the particular gas expressed in Gg CO₂ Equivalents calculated according to CO₂ Equivalent type that is set as default.




Figure 4.8 – Time Series window

4.3 Working with the grid



Figure 4.9 - Worksheet grid

The worksheet grid represents a powerful tabular tool comprising of:

- Worksheet identification text on top with indication of currently chosen Inventory Year (top-right)
- Worksheet specific parameters (Gas, fuel type, calculation type, parameters, etc.).
- Top header of the grid - column headers are not editable by user.
- Navigation/Row status column (left-most) – indicates the active row that is selected and its status if it is in edit mode, if it is a new row, or if it is just selected.
- Rows of the grid containing data (e.g. activity data, emission factors, emissions, ...). Each row represents one particular activity. There are different types of cells in the row like editable cells, calculated value cells and text cells. The different types of cells are distinguished by different color. There could be additional icon placed in the cell to highlight some warning to the user.
- Small button with the key icon which allows setting the Notation Key for related parameter.
- Editable cells (white background) - fields enabling to edit activity data, emission factors and other parameters.
- Calculated cells (green background) – e.g. emissions calculated from activity data and emission factors using the relevant formula. These are not editable but automatically calculated.
- Column containing iconic action buttons:
 - this action button can be used to edit remark for currently selected record. If record already contains some remark, the action button will be coloured green

-  - this action button saves current row changes into database.
-  - this action button undoes all current row changes.
-  - this action button deletes current row from database.
- Summary row on the bottom showing totals of activity data and emissions in the worksheet where applicable.

4.3.1 Row Status column

Left-most column of the grid is the Row Status column that indicates the current activity being performed within selected row. There are several icons indicating the status as follows:

-  - indicates active row. This row is just selected - not in edit mode.
-  - Currently selected row is in edit mode. Edit mode is activated as soon as a value in any cell is changed by user.
-  - indicates that the row is an "add-new" row that is used as a "template" for new row.
-  - "add-new" row in edit mode. Edit mode is activated as soon as user starts to enter values into cells of "add-new" row.

4.3.2 Adding new row

If the worksheet allows the user to add new rows, the "add-new" row can be found as the last row of the grid marked with  Status Row icon. This row acts as a "template" for the new row.

As soon as the user starts entering data in cells of an "add-new" row, edit mode is activated and Status Row icon changes to . After filling all the required cells, new row is saved into database automatically after navigating to another row or after pressing the  button or after grid loses focus. Validation of entered data is performed before the new row is stored into database. In case of any error in the supplied data, user will be informed to correct it.

4.3.3 Canceling adding new row

Adding of new row can be canceled anytime using the ESC (Escape) key or  or  action buttons.

In case of using ESC key the behavior is as follows:

- If the active cell is in edit mode, hitting ESC cancels editing of that cell and undoes changes on that cell. New row remains in edit mode.
- Pressing ESC again (while none of the cells is in edit mode) cancels adding new row removing it from the worksheet.

In case of using iconic action buttons the new row will be cancelled immediately no matter if any cell is in edit mode.

4.3.4 Editing existing row

Edit mode () is activated as soon as the user starts modifying data in editable cells. Modified row is saved into database as soon as the user leaves the row being edited or by pressing the  button or after grid loses focus. Validation of entered data is performed before the row is updated in the database. In case of any error in the supplied data, user will be informed to correct it.

4.3.5 Canceling editing existing row / Undoing cell changes

ESC key or  action button can be used to undo row changes.

In case of using ESC key the behavior is as follows:


- If the active cell is in edit mode, hitting ESC cancels edit mode of that cell and undoes changes made to cell data (if any).
 - If there are no more cells changed in edited row this also cancels row editing.
 - If there are more cells that have been changed while editing row hitting ESC again undoes changes in all changed cells and cancels row editing returning it to its original state.

In case of using  action button changes in all cells will be undone automatically at once and edit operation on row will be canceled.

4.3.6 Deleting rows

Pressing the **Delete selected rows** button or hitting the DEL key deletes all rows selected. More rows can be selected at the same time using mouse or Shift key function within Row Status column of the grid. **Iconic action button  at row level can be used to delete just the corresponding row.**

In all cases user is provided with the confirmation dialog.




The screenshot shows a data grid with columns for Subdivision, Fuel, and Consumption Unit. A confirmation dialog box titled 'Delete Rows' is overlaid on the grid. The dialog contains a question mark icon and the text: 'You have selected 4 rows for deletion. Choose Yes to delete the rows or No to exit.' There are 'Yes' and 'No' buttons at the bottom. The grid rows include entries like 'Unspecified' for Subdivision and 'Anthracite' for Fuel.

Figure 4.10 - Deleting multiple rows

4.3.7 Value List cells

Some of the cells contain Value List where user can choose from the predefined set of values or nomenclature data (e.g. emission factors). Such cells have the Value List indicator  which when clicked will provide the user with the predefined set of nomenclature data. Some of the Value Lists are fixed and user cannot enter data other than that in the list (e.g. Fuels). Some are editable (e.g. emission factors Value Lists) and user is able to enter custom data that are not contained in the value list.



The screenshot shows a data grid with various columns for Fuel consumption, CO2 emissions, CH4 emissions, and N2O emissions. A specific cell in the CO2 Emissions row for Motor Gasoline is highlighted with a blue background and contains the value '66450'. A tooltip or value list is displayed below this cell, showing 'Default Value: 3.2', 'Lower limit: 0.96', 'Upper limit: 11', 'Unit: kg/TJ', and 'Parameter: Uncontrolled'. The tooltip also contains a detailed description: 'Motor gasoline uncontrolled default value is based on USEPA (2004b) value for a USA light duty gasoline vehicle (car) - uncontrolled, converted using values and assumptions described in table note (a). If motorcycles account for a significant share of the national vehicle population, inventory compilers should adjust the given default emission factor downwards.' Another row in the grid shows a parameter 'Oxidation Catalyst' with a value of '8'.

Figure 4.11 - Value List containing emission factors

4.3.8 Notation Keys

Notation Keys can be set by clicking the  button of the particular cell. This enables to set Activity Data and Emissions Notation Keys.

Activity Data Notation Keys

Can be one of: **IE, NO, C**

- **IE** – Activity is included elsewhere: all Activity Data and Emission Factor related columns will be blank and not editable in this case.
- **NO** – Activity is not occurring: the same as for IE
- **C** – Activity data are confidential: they will not be exposed in reporting tables.

Emissions Notation Keys

Can be **NE**: this means that emissions are not estimated. All Emission Factor related cells will be blank and not editable. Activity Data remain editable.

4.3.9 Numeric values precision

All decimal values are stored as “double” type in the database. All calculations are performed with full precision relevant for “double” type (see table below). Presentation of numbers in the grids can be adjusted in the software preferences to e.g., limit number of displayed decimal places by rounding and/or show/hide thousands separator.

C# type/keyword	Approximate range	Precision	Size
double	$\pm 5.0 \times 10^{-324}$ to $\pm 1.7 \times 10^{308}$	~15-17 digits	8 bytes

4.4 Time Series Data Entry

Majority of worksheets supports time series data entry. This means that parameters of worksheets can be edited across existing inventory years. Time series data entry worksheet can be activated by pressing the **Time Series Data Entry** button located under the grid. This will open the following window.




Figure 4.12 – Time Series Data Entry

4.4.1 Parameters

Parameter list contains the list of all editable parameters contained in the worksheet. By choosing the particular parameter the grid will display the selected parameter values across existing inventory years grouped by all available combinations of row identifiers. Values in white cells are editable.

4.4.2 Row Identifiers

Grid columns preceding years are so called „Row Identifiers“ that uniquely identify the Worksheet rows across all existing years representing all existing combinations of identifiers across years. In case parameter value is not editable within the particular row (shaded), this means that the combination of relevant row identifiers does not occur in that particular year.

4.4.3 Export to Excel

It is possible to export the selected parameter data into Excel by clicking the **Export to Excel** button. Data for that parameter then can be modified in Excel and imported back into the software. Example of exported XLS is in the following figure.

A	B	C	D	E	F	G	H	I	J	K	L	M	N	O	P
1 Generated:	4.11.2022 9:48:04														
2 Country:	Slovakia														
3 Sector:	Energy														
4 Category:	Fuel Combustion Activities														
5 Subcategory:	1.A.1.a.i - Electricity Generation														
6 Sheet:	Fuel Consumption Data														
7 Parameter:	Consumption (Mass, Volume or Energy Unit)														
8															
9 Subdivision	Fuel	Fuel GUID	1980	1981	1982	1983	1984	1985	1986	1987	1988	1989	1990	1991	1992
10 Unspecified	Crude Oil	00000001-0000-0000-0000-000000000000	260							260	260	260	260	260	260
11 Unspecified	Orimulsion	00000002-0000-0000-0000-000000000000	350							350	350	350	350	350	350
12 Unspecified	Natural Gas Liquids	00000003-0000-0000-0000-000000000000													
13 Unspecified	Motor Gasoline	00000004-0000-0000-0000-000000000000													
14 Unspecified	Anthracite	00000017-0000-0000-0000-000000000000	4100							4100	4100	4100	4100	4100	4100
15 Unspecified	Coking Coal	00000018-0000-0000-0000-000000000000	2200							2200	2200	2200	2200	2200	2200
16 Unspecified	Other Bituminous Coal	00000019-0000-0000-0000-000000000000	3100							3100	3100	3100	3100	3100	3100
17 Unspecified	Sub-Bituminous Coal	0000001a-0000-0000-0000-000000000000	4100							4100	4100	4100	4100	4100	4100
18 Unspecified	Lignite	0000001b-0000-0000-0000-000000000000	5100							5100	5100	5100	5100	5100	5100
19 Unspecified	Oil Shale / Tar Sands	0000001c-0000-0000-0000-000000000000	580							580	580	580	580	580	580
20 Unspecified	Brown Coal Briquettes	0000001d-0000-0000-0000-000000000000	650							650	650	650	650	650	650
21 Unspecified	Coke Oven Coke / Lignite Coke	0000001f-0000-0000-0000-000000000000													3000
22 Unspecified	Biogasoline	0000002f-0000-0000-0000-000000000000													1500
23 Unspecified	Biodiesels	00000030-0000-0000-0000-000000000000													1000
24 Unspecified	Other Biogas	00000034-0000-0000-0000-000000000000													
25 Unspecified	Custom Liquid	ac0c89d5-3011-4146-b1c5-6ada808d17b3	1500							1500	1500	1500	1500	1500	1500

Figure 4.13 – Exported parameter in Excel

4.4.4 Import from Excel

Pressing the **Import from Excel** button allows importing of previously exported parameter back into the software. Software asks for the input XLS file and if it meets the conditions it will be imported. The format of data as Excel file can be obtained by exporting Excel file. See Chapter 4.4.3.

4.4.5 Copy and Paste functions

Time Series Data Entry table implements the Copy and Paste functions which can be used to transfer data from/to table between the IPCC Inventory Software and other third party software (e.g. Microsoft Excel).

Copy function

Data can be copied into the clipboard by highlighting desired cells and pressing **Ctrl+C** keys. Data stored in the clipboard can than be pasted into any third-party software that supports data pasting. There are 2 ways of highlighting cells to be copied:

- **Using mouse** – use left-most column to highlight cells by rows or column headers to highlight cells by columns
- **Using keyboard** – click the starting cell from which you want to start highlighting the region. If the cell is editable it will switch to edit mode disabling the highlighting function. Therefore it is necessary to press **ESC** to exit edit mode. While cell is not in edit mode but selected, use **Shift+keyboard** arrows to highlight the desired region of cells.

Paste function

Data can be pasted from clipboard into the Time Series Data Entry table in case the structure of data is tabular – e.g. copied from **Microsoft Excel**.

- 1) Select the starting cell for which data paste should start.
- 2) If the cell is editable it will switch to edit mode. It is necessary to exit edit mode using **ESC** key before pasting data.
- 3) If you decide to define a paste region by highlighting cells using the **Shift+keyboard** arrows be sure your region matches the structure stored in the clipboard – number of columns and rows must match.
- 4) Use **Ctrl+V** to paste data. Cells that are read-only (automatically calculated green cells or other non-editable cells) will be ignored.

Important: only existing rows can be updated by pasting data. If source data in clipboard contains more rows or columns than Time Series Data Entry table, those will not be created. Creating of new rows by pasting data is not supported, thus not possible.

4.4.6 Chart

Chart at the bottom of the Time Series Data Entry window contains the visual representation of selected parameter values for the selected grid row across all years. It can be used for visual checking of value variations across all years.




Figure 4.14 – Time Series Chart

5 Example Worksheets

5.1 Fuel Combustion Activities and Emissions

This set of worksheets covers all categories within the category 1.A – Fuel Combustion Activities. Worksheets are available for each sub-category at the most disaggregated level.

Worksheet		Sector: Energy		Category: Fuel Combustion Activities		Subcategory: 1.A.1.a.i - Electricity Generation		Sheet: Fuel Consumption Data		1990	
Data		Fuel Type		(All fuels)							
Equation 2.4											
Subdivision		Fuel		Consumption Unit		Consumption (Mass, Volume or Energy Unit)		Conversion Factor (TJ/Unit) (NCV)		Total consumption (TJ)	
S	Δ	F	Δ	U	Δ	C	CF	TC = C * CF			
►	Unspecified	Anthracite		Gg (Auto CF)		4100	26.7	109470			
►	Unspecified	Biodiesels		Gg (Auto CF)		1000	27	27000			
►	Unspecified	Biogasoline		Gg (Manual CF)		1500	26.3	39450			
►	Unspecified	Brown Coal Briquettes		Gg (Auto CF)		650	20.7	13455			
►	Unspecified	Coke Oven Coke / Lignite Coke		Gg (Auto CF)		3000	28.2	84600			
►	Unspecified	Coking Coal		Gg (Auto CF)		2200	28.2	62040			
►	Unspecified	Crude Oil		Gg (Auto CF)		260	42.3	10998			
►	Unspecified	Custom Liquid		Gg (Auto CF)		1500	43	64500			
►	Unspecified	Lignite		Gg (Auto CF)		5100	11.9	60690			
►	Unspecified	Oil Shale / Tar Sands		Gg (Auto CF)		580	8.9	5162			
►	Unspecified	Orimulsion		Gg (Auto CF)		350	27.5	9625			
►	Unspecified	Other Bituminous Coal		Gg (Auto CF)		3100	25.8	79980			
►	Unspecified	Sub-Bituminous Coal		Gg (Auto CF)		4100	18.9	77490			
*											
Total								644460			
Fuel Manager... Time Series data entry...											

Figure 5.1 – Example of Fuel Combustion Activities – Activity Data

Worksheet		Sector: Energy		Category: Fuel Combustion Activities		Subcategory: 1.A.1.a.i - Electricity Generation		Sheet: Fuel Combustion Emissions		1990	
Data		Fuel Type		(All fuels)							
Equation 2.4											
Subdivision		Fuel		Total consumption (TJ)		CO2 Emissions (Gg CO2)		CH4 Emissions (Gg CH4)		N2O Emissions (Gg N2O)	
S	Δ	F	Δ	TC		CO2		CH4		N2O	
►	Unspecified	Anthracite		109470		10760.901		0.10947		0.16421	
Technology				CO2		CH4		N2O			
Type of Technology	Technology penetration (%)	Consumption (TJ)	CO2 Emission Factor (kg CO2/TJ)	Amount Captured (Gg CO2)	CO2 Emissions (Gg CO2)	CH4 Emission Factor (kg CH4/TJ)	CH4 Emissions (Gg CH4)	N2O Emission Factor (kg N2O/TJ)	N2O Emissions (Gg N2O)		
T	P	C=TC* (P/100)	EF(CO2)	Z	CO2=C*EF (CO2)/10^6*Z	EF(CH4)	CH4=C*EF (CH4)/10^6	EF(N2O)	N2O=C*EF (N2O)/10^6		
►	Unspecified	100	109470	98300	10760.9	1	0.10947	1.5	0.16421		
*											
Total				109470		10760.901		0.10947		0.16421	
Equation 2.4											
Subdivision		Fuel		Total consumption (TJ)		CO2 Emissions (Gg CO2)		CH4 Emissions (Gg CH4)		N2O Emissions (Gg N2O)	
S	Δ	F	Δ	TC		CO2		CH4		N2O	
►	Unspecified	Biodiesels		27000		0		0		0	
►	Unspecified	Biogasoline		39450		0		0		0	
►	Unspecified	Brown Coal Briquettes		13455		1311.8625		0.01346		0.02018	
►	Unspecified	Coke Oven Coke / Lignite Coke		84600		0		0		0	
►	Unspecified	Coking Coal		62040		5868.984		0.06204		0.09306	
►	Unspecified	Crude Oil		10998		806.1534		0.03299		0.0066	
*											
Fuel Manager... Time Series data entry...											

Figure 5.2 – Example of Fuel Combustion Activities - Emissions

5.1.1 Fuel Type

Fuel Type selection box can be used to choose the desired Fuel Type to work with. After selecting the Fuel Type only the list of fuels of the selected type is available in the **Fuel** column in the grid to choose from and the worksheet will contain only rows with fuels of the selected type.

Fuel Type		Liquid Fuels
	Liquid Fuels	A Consumpt on (Mass, Volume or Energy Unit)
	Fuel	90
t	Crude Oil	200
t	Emulsion	100
t	Natural Gas Liquids	150
t	Motor Gasoline	50
t	Aviation Gasoline	300
t	Jet Gasoline	
t	Jet Kerosene	
t	Other Kerosene	

Figure 5.3 – Expanded list of available Liquid fuels

It is possible to display all fuels in the **Fuel** list by selecting the last item in the **Fuel Type** selection box labeled **(All)**. In this case, worksheet will contain rows with fuels of any type.

5.1.2 Uncertainties for Fuel Type

Button **Uncertainties for Fuel Type** can be used to enter Activity Data and Emission Factor uncertainties at the fuel type level that is currently selected. User will be provided with the dialog box where uncertainties can be defined.




Figure 5.4 – Uncertainties for Liquid Fuels

Default Activity Data uncertainties are prefilled according to *2006 IPCC Guidelines*. Default Emission Factor uncertainties are computed from default values for selected IPCC Category, Fuel Type and Gas. Default values can be changed and are stored into database automatically after pressing the **OK** button.

6 UNFCCC CRT

6.1 Introduction

Since version v2.86, the IPCC Inventory Software is capable of exporting data into Common Reporting Tables format (CRT). Interface is accessible from the Main Menu / Export / UNFCCC CRT.

6.2 CRT Data Set management


6.2.1 What is CRT Data Set

CRT Data Set represents a particular instance of CRT export which holds CRT Tables with data for the set of years that were selected during CRT Data Set creation. Software allows maintaining multiple CRT Data Sets that are independent of each other and thus can be managed and exported to JSON independently.

6.2.2 CRT Data Set management screen

This screen is designed for CRT Data Set management. It provides the following functionality:

- Create new CRT Data Set
- Edit properties of existing CRT Data Set
- Open tables interface that allows managing data across sectors and years for selected CRT Data Set
- Generate JSON (export format) for selected CRT Data Set
- Refresh values – compile CRT Variable values from IPCC Inventory Software worksheet data for selected CRT Data Set
- Delete existing CRT Data Set




The screenshot shows a window titled 'CRT Data Set Manager'. At the top, there is a table with two columns: 'CRT Data Set name' and 'Date created'. The table contains four rows, each representing a different CRT Data Set. The second row, 'Test 1995 - 2000', is highlighted with a blue background, indicating it is the currently selected item. At the bottom of the window, there is a row of buttons: 'New CRT Data Set', 'Edit CRT Data Set', 'Open tables', 'Generate JSON', 'Refresh values', 'Delete CRT Data Set', and 'Close'.

CRT Data Set name	Date created
Test 1990 - 1994	12.05.2023 13:23:07
Test 1995 - 2000	17.05.2023 08:22:13
Test 2001 - 2005	17.05.2023 08:27:30
UNFCCC JSON Test (SVK-1990)	16.05.2023 10:07:36

Except for “New CRT Data Set” button, all the action buttons at the bottom of the table always apply to currently selected CRT Data Set in table (highlighted).


6.2.2.1 New CRT Data Set

This action button opens screen where properties of new CRT Data Set are specified.



- Name – name of new CRT Data Set
- Years – inventory years assigned to new CRT Data Set


After pressing Save, new data set is created and user is prompted whether to feed data into tables of new data set. This operation can be postponed and carried out later on various levels (at sector level, table level, cell level, cell selection level)




6.2.2.2 Edit CRT Data Set

This action button opens screen where properties of existing CRT Data Set can be adjusted.

- Name – can be changed if necessary
- Years:
 - o Adding additional years – user can add additional years to existing CRT Data Set. After adding new years and saving data set user is prompted whether to feed data into CRT tables for newly added years within all sectors.



- Deleting existing years – user can remove existing years from edited data set. **Note that all data belonging to removed years will be permanently deleted.**



6.2.2.3 Open tables

This action button opens screen containing CRT Tables for currently selected CRT Data Set. This screen will open in a mode that allows user to switch between itself and other software screens (e.g. Worksheets screen). Only one CRT Tables screen for one CRT Data Set can be open at a time. Refer to the “CRT Tables” chapter for more information on CRT Tables screen and its functions.

TABLE 1.A(a) SECTORAL BACKGROUND DATA FOR ENERGY
Fuel combustion activities - sectoral approach (Sheet 4 of 4)

GREENHOUSE GAS SOURCE AND SINK CATEGORIES	AGGREGATE ACTIVITY DATA			IMPLIED EMISSION FACTORS			EMISSIONS			AMOUNT
	(TJ)	NCV/GCV	CO2	CH4	N2O	(kt)	CH4	N2O		
									(t/TJ)	
1.A.4 Other sectors	484,252.9					22,256.99097	16,369517	1,254897		
Liquid fuels	318,112.9					15,006.19097	16,112117	1,240461		
Solid fuels	NO					NO	NO	NO, FX		
Gaseous fuels (6)	NO					NO	NO	NO		
Other fossil fuels (7)	161,100					7,250.8	0.2322	0.013932		
Peat (8)	NO					NO	NO	NO		
Biomass(3)	5,040					200	0.0252	0.000504		
1.A.4.a. Commercial/institutional (14)	126,540					5,009.035	12,6417	0.499434		
Liquid fuels	76,500					5,009.035	12,6165	0.49893		
Solid fuels	NO					NO	NO	NO, FX		
Gaseous fuels (6)	NO					NO	NO	NO		
Other fossil fuels (7)	45,000					NE, NO	NE, NO	NE, NO		
Peat (8)	NO					NO	NO	NO		
Biomass (3)	5,040					200	0.0252	0.000504		
1.A.4.a.i. Stationary combustion	15,090					811,035	0.1257	0.006534		
Liquid fuels	10,050	NCV				811,035	0.1005	0.00603 C		
Solid fuels	NO	NCV				NO	NO	FX		

Legend

- The IEFs for CO2 are estimated on the basis of gross emissions, i.e. CO2 emissions plus the absolute amount captured.
- Final CO2 emissions after subtracting the amounts of CO2 captured.
- Although CO2 emissions from biomass are reported in this table, they will not be included in the total CO2 emissions.





Documentation box

- Parties should provide a detailed description of the fuel combustion subsector in the relevant section of chapter 3 ("Energy" (CRT subsector 1.A)) of the NID. Use this documentation box to provide references to relevant sections
- To implement the first note, users can mark values mapped in this CRT with the notation key "C". Note that Totals calculated in orange cells will not change.
- Please describe in the "Documentation Box" the liquid fuels included in the estimates reported in row "Other liquid fuels [IPCC Software 1.A.4.c.ii]" and "Other liquid fuels [IPCC Software 1.A.4.c.iii]".
- Please describe in the "Documentation Box" the other fossil fuels included in the estimates reported in row "Other fossil fuels [IPCC Software 1.A.4.c.ii]" and "Other fossil fuels [IPCC Software 1.A.4.c.iii]".

IPCC Inventory Software notes


6.2.2.4 Generate JSON

This action button serves for the purpose of generating export in JSON format. All CRT tables that belong to selected CRT Data Set will be serialized into JSON file for either all sectors or specific sector, and for selected years.




6.2.2.5 Refresh values

This action button allows refreshing all CRT Variable values within selected CRT Data Set for all sectors and selected years. Fresh values are compiled from the IPCC Inventory Software worksheets replacing current CRT Variable values. Other information that was already added by user such as CRT Variable description and comments will be preserved. Notation Key specific comments will be preserved only in case refreshed variable Notation Key doesn't change during refresh.



6.2.2.6 Delete CRT Data Set

This action will permanently delete existing CRT Data Set together with all data in all CRT Tables. **This action is not reversible.**



6.3 CRT Tables

Screen containing CRT Tables can be open using “Open tables” button in CRT Data Set Manager for selected CRT Data Set. Alternative way is to double-click desired CRT Data Set row in CRT Data Set Manager table. Only one CRT Tables screen of one particular CRT Data Set can be open at a time.

CRT Tables - Test 1990 - 1994

Sector: Energy | Year: 1990 | Refresh values

Table1 | Table1.A(s1) | Table1.A(s2) | Table1.A(s3) | Table1.A(s4) | Table1.A(b) | Table1.A(c) | Table1.A(d) | Table1.B.1 | Table1.B.2 | Table1.C | Table1.D

TABLE 1.D SECTORAL BACKGROUND DATA FOR ENERGY

International aviation and international navigation (international bunkers) and multilateral operations

Log column widths

GREENHOUSE GAS SOURCE AND SINK CATEGORIES

	ACTIVITY DATA	IMPLIED EMISSION FACTORS			EMISSIONS		
		Consumption	CO2	CH4	N2O	CO2	CH4
	(TJ)	(t/TJ)	(kg/TJ)	(kg/TJ)	(kt)	(kt)	(kt)
1.D.1.a. International aviation (aviation bunkers)	660,700				39,209,101542	0,320022	
Jet kerosene	456,000				32,603,995547	0,2205	
Aviation gasoline	94,200				6,594,01804	0,047092	
Biomass	110,500				11,087955	0,052429	
1.D.1.b. International navigation (marine bunkers)	279,305,5				13,885,63975	1,206939	
Residual fuel oil	NO				FX	NO	
Gas/diesel oil	102,705,5				7,534,23975	0,718939	
Gasoline	88,600				NE	NE	
Other liquid fuels (please specify)	21,000				1,694	0,105	
Other liquid fuels [IPCC Software 1.A.3.d.i]	21,000				1,694	0,105	
Gaseous fuels (1)	24,000				1,346,4	0,168	
Biomass	NO				NO	NO	
Other fossil fuels (please specify) (2)	43,000				3,311	0,215	
Other fossil fuels [IPCC Software 1.A.3.d.i]	43,000				3,311	0,215	
1.D.2. Multilateral operations (3)	299,900				15,403,292165	1,5505	
Additional information							
Fuel consumption	Domestic distribution (%) (a)	International distribution (%) (a)					
Aviation							
Marine							

Legend: (1) Including LNG for international navigation. (2) Include information in the documentation box on which fuels are included and provide a reference to the section in the NID where further information is provided. (3) Parties may choose whether to report or not report AD and IEFs for multilateral operations, consistently with the principle of confidentiality stated in the MPGs (chapter II). In any case, Parties should report the emissions from multilateral operations, where available, under memo items in the summary tables and in the sectoral report table for energy.

Documentation box: Parties should provide a detailed description of the fuel combustion subsector, including international aviation and international navigation, in the relevant section of chapter 3 ("Energy" (CRT subsector 1.A)) of the NID. Use this documentation box to provide references to relevant sections of the NID, if any additional information and/or documentation is required.

IPCC Inventory Software notes: Orange cells above that contain no information (i.e. are blank) will be calculated automatically by the UNFCCC reporting tool. No action by the user is required.

Note that in CRT Reporting, it is not necessary to enter data for some fuel types used as international bunkers. The IPCC Inventory software may include additional fuels for bunkers not included here.

Please report in the "Documentation Box" the other liquid fuels included in the estimates reported in.

Save

CRT Tables screen consists of the following elements.


- Window title – contains the name of selected CRT Data Set
- Sector – currently selected sector. Set of tables is presented according to selected Sector
- Year – currently selected year from the list of years that belong to selected CRT Data Set
- Refresh values – allows refreshing values from the IPCC Inventory Software worksheets for all tables in selected sector and for years selected by user
- Tabbed interface – allows switching between tables belonging to selected sector
- Documentation area – relevant for currently selected table. Contains Legend, Documentation box, IPCC Inventory software notes and other relevant info. Documentation area windows can be rearranged according to user preference.

6.3.1 CRT Table actions

For each CRT Variable in CRT Table there are several actions. Actions can be performed for a single cell as well as for selection of cells.

6.3.1.1 Single-cell actions

Right click on any cell that represents CRT Variable to open context menu with actions that are relevant for selected CRT Variable.



Edit

Opens CRT Variable detail dialog with all information relevant for the type of selected CRT Variable. Detail dialog can be alternatively open by double-click on a cell. Standard numeric variable detail dialog is shown below.

CRT Variable Detail

Summary	Description	Party comment	User comment	Official comment
UID: 3207d352-5c2c-45de-a90f-e10de05c1a24				
Value: 456,000				

CRT Variable Detail

Summary	Description	Party comment	User comment	Official comment
Variable description:				

- Summary – contains basic information such as UID and current value
- Description – description of variable
- Party comment
- User comment
- Official comment

User can enter this additional information independently for every CRT Variable cell in every CRT Table. In case of CRT Variable that has Notation Key instead of numeric value, additional information that is relevant for selected Notation Key becomes available. Example for FX variable below.

CRT Variable Detail

Summary	Description	Party comment	User comment	Official comment	FX
MPG Flexibility Provision:					
<input type="text"/>					
Description of the application of flexibility:					
<input type="text"/>					
Clarification of capacity constraint:					
<input type="text"/>					
Timeframe for improvement:					
<input type="text"/>					
Progress made in addressing areas of improvement:					
<input type="text"/>					

Save Cancel


Example of detail dialog for “Method” and “EF” CRT Variable:

Selected	Notation	Remark
<input checked="" type="checkbox"/>	T1	IPCC Tier 1 methodological approach
<input checked="" type="checkbox"/>	T2	IPCC Tier 2 methodological approach
<input checked="" type="checkbox"/>	T3	IPCC Tier 3 methodological approach
<input type="checkbox"/>	CR	CORINAIR
<input type="checkbox"/>	CS	Country-Specific
<input type="checkbox"/>	M	Model
<input type="checkbox"/>	RA	IPCC Reference Approach
<input type="checkbox"/>	OTH	Other


Selected	Notation	Remark
<input checked="" type="checkbox"/>	D	IPCC Default
<input type="checkbox"/>	CR	CORINAIR
<input type="checkbox"/>	CS	Country-Specific
<input type="checkbox"/>	M	Model
<input type="checkbox"/>	PS	Plant-Specific
<input type="checkbox"/>	OTH	Other

Notation Key

This menu item contains list of applicable Notation Keys that can be set for CRT Variable. If cell already contains one of the notation keys instead of numeric value, then the list of applicable notation keys is as follows:




In case of cells that contain numeric value the list of notation keys contains only one item – C (Confidential) allowing a user to mark that CRT Variable as Confidential.



A “C” flag is added as suffix to numeric value. While value in confidential cell is still visible in the software it WILL NOT be exported in JSON. Choosing “C” on a cell that already has “C” flag will remove it.

Refresh value

This action allows refreshing CRT Variable with relevant IPCC Inventory Software worksheet value. Action can be performed for current year, all years in data set or only years explicitly selected by user.



6.3.1.2 Multi-cell actions


CRT Table interface allows performing actions on multiple selected cells at once. This way it is possible to e.g. set the same documentation text for several cells without editing each cell individually.

Multiple cells can be selected utilizing various techniques.

- Left click and hold on starting cell and drag mouse pointer to select additional cells

- Left click on column header to select single column or left click, hold and drag to select multiple columns and all of their cells
- Left click on row header to select single row or left click, hold and drag to select multiple rows and all of their cells.
- Hold CTRL and left click on individual cells to be selected
- Click on start cell, hold SHIFT and then click on end cell to select area of cells

Selected cells are highlighted. In case selection contains at least one CRT Variable cell, right click anywhere within selection opens context menu that applies to selection.




A screenshot of a spreadsheet application showing a context menu. The menu is titled 'Edit' and includes options: 'Notation Key' and 'Refresh values'. The spreadsheet has several rows of data, with some cells highlighted in orange. The first row contains values 257, 0.006534, and -75.184. The second row contains 005, 0.00603 C, NE, and D. The third row contains NO, NO, NO, and NO. The fourth row contains NO, NO, NO, and NO. The fifth row contains NO, NO, NO, and NO. The sixth row contains 252, 0.000504, and -75.184. The seventh row contains 516, 0.4929, and NO. The eighth row contains 516, 0.4929, and NO. The ninth row contains NO, NO, and NO. The tenth row contains NO, NO, and NO.


Edit

Opens detail dialog for selected cells in multi-cell mode. Detail dialog is constructed based on types of cells that are in selection. This means all relevant tabs will be shown within detail dialog. (e.g. if selection contains "Method" and "EF" cell, "Method" and "EF" tabs will become available).

User has to explicitly flag which information entered in multi-cell detail dialog should be applied to selected cells. This way it is possible to bulk-update only specific type of information while leaving other information in selected cells intact. Example: If only "Party comment" should be updated in all selected cells then user explicitly marks that comment using a dedicated checkbox and then inputs new value for that comment (see screenshot below).




In multi-cell detail dialog, each piece of information has its dedicated "Apply" checkbox. Example for FX related comments below where only "MPG Flexibility Provision" was marked to be updated within all FX cells in the selection of cells.



Note, that every piece of information will be applied to cell in selection only in case it is relevant for that cell. (e.g. FX comments will be applied only to those cells in selection that are FX).


Notation key

Allows to set the same Notation Key for all cells in selection. The rules are analogic to those in "Edit" action and thus selected Notation Key will be applied only to relevant cells. (e.g. if C is selected, only cells containing real numeric value will be marked as C).



Refresh values

Allows refreshing values from the IPCC Inventory Software worksheets for all selected cells for either current year, all years in data set or for years explicitly selected by user.



6.3.1.3 Editable cells

Some cells highlighted with pale green color allow direct editing of value. User is allowed to change value of such cells or set notation key by direct input.

- To enter numeric value – type in numeric value directly into cell. Value can be marked as confidential by entering “c” or “C” after numeric value
- To enter notation key – type in one of the relevant notation keys directly. Allowed notation keys: NE, NA, NO, IE, FX (can be typed lowercase in which case they will be automatically converted to upper case)

1.A.1.c.i. Manufacture of solid fuels	77,477.485
Liquid fuels	NO
Solid fuels	29,477.485 C

6.3.2 CRT Table Documentation Box

Allows to specify additional textual information at CRT Table level. Each documentation box has its dedicated UID thus it is exported to JSON just like any other CRT Variable. After changing value of documentation box, click Save button located next to editing text area to apply changes.

Documentation box

• Parties should provide a detailed description of the fuel combustion subsector, including international aviation and international navigation, in the relevant section of chapter 3 ("Energy" (CRT subsector 1.A)) of the NID. Use this documentation box to provide references to relevant sections of the NID, if any additional information and/or further details are needed to explain the contents of this table.

• Provide in this documentation box a brief explanation of how the consumption of international aviation and

1.D.1
Documentation for 1.D.1

1.D.2
Documentation for 1.D.2

Save

Annex 1

The table below shows the details on mapping of the emission estimates based on the *2006 IPCC Guidelines* to the NAI reporting tables in this software. The format of these NAI reporting tables follows the Tables 1 and 2 of Annex to Decision 17/CP.8 of the UNFCCC (Guidelines for the preparation of national communications from Parties not included in Annex I to the Convention) which are based on the *Revised 1996 Guidelines* reporting structure, but some modifications have been made in order to help software users report emission estimates in a more transparent manner. Additional explanation is provided in the column “Note” of the table below for some categories where mapping is not straightforward.

The function of exporting to NAI reporting tables in this software is intended to help software users report emission estimates in accordance with Annex to Decision 17/CP.8 of the UNFCCC, but is not intended to prescribe the way of mapping between categories under the *Revised 1996 IPCC Guidelines* and those under the *2006 IPCC Guidelines*. Software users may wish to use different mapping approach for some categories.

2006 Category most disaggregated level (Emissions are calculated at this level.)		1996 Category Second Level (Emissions are reported at this level in NAI table.)	Note
1.A.1	Energy Industries	1A1	
1.A.2	Manufacturing Industries and Construction	1A2	
1.A.3	Transport	1A3	The emissions under 1.A.3.b.vi (Urea-based catalysts) is excluded, since they are already reported under 2B of 1996 GLs. See note for category 2.B.1.
1.A.4	Other Sectors	1A4	
1.A.5	Non-Specified	1A5	The emissions under 1.A.5.c (Multilateral Operations) is included under Memo Item.
1.B.1	Solid Fuels	1B1	
1.B.2	Oil and Natural Gas	1B2	
1.B.3	Other emissions from Energy Production	7	
1.C	Carbon dioxide Transport and Storage	7	
2.A.1	Cement Production	2A	
2.A.2	Lime Production	2A	
2.A.3	Glass Production	2A	
2.A.4.a	Ceramics	2A	
2.A.4.b	Other Uses of Soda Ash	2A	
2.A.4.c	Non Metallurgical Magnesia Production	2A	
2.A.4.d	Other (please specify)	2A	According to the 2006GLs, CO2 emissions calculated in this category (2.A.4.d) should be reported in other relevant categories where the carbonates are used. This allocation to other categories is implemented in the second tab in the worksheet for this category. However, this allocation to other categories is not necessary according to the 1996GLs, therefore for the purposes of mapping back to 1996GLs reporting tables, all the CO2 emissions calculated in the first tab are included in 2A of

		1996GLs.
--	--	----------

2006 Category most disaggregated level (Emissions are calculated at this level.)		1996 Category Second Level (Emissions are reported at this level in NAI table.)	Note
2.A.5	Other (please specify)	2A	
2.B.1	Ammonia Production	2B	According to the 2006GLs, CO2 emissions subsequently used for urea production should be deducted. Later emissions of CO2 from such urea should be reported in the other categories like 1.A.3.b.vi (Urea-based catalyst), 3.C.3 (Urea application). For the purposes of mapping back to 1996GLs reporting tables, CO2 emissions before subtracting CO2 used for urea production are included in 2B1 of 1996GLs.
2.B.2	Nitric Acid Production	2B	
2.B.3	Adipic Acid Production	2B	
2.B.4	Caprolactam, Glyoxal and Glyoxylic Acid Production	2B	
2.B.5	Carbide Production	2B	
2.B.6	Titanium Dioxide Production	2B	
2.B.7	Soda Ash Production	2A	
2.B.8.a	Methanol	2B	
2.B.8.b	Ethylene	2B	
2.B.8.c	Ethylene Dichloride and Vinyl Chloride Monomer	2B	
2.B.8.d	Ethylene Oxide	2B	
2.B.8.e	Acrylonitrile	2B	
2.B.8.f	Carbon Black	2B	
2.B.9.a	By-product emissions	2E	Details are the same as the instructions for 2F shown below.
2.B.9.b	Fugitive Emissions	2E	
2.B.10	Other (Please specify)	2B	
2.C.1	Iron and Steel Production	2C	
2.C.2	Ferroalloys Production	2C	
2.C.3	Aluminium production	2C	CO2 is included in Table 1. CF4 and C2F6 are included in Table 2.
2.C.4	Magnesium production	2C	CO2 is included in Table 1. SF6 is included in Table 2.
2.C.5	Lead Production	2C	
2.C.6	Zinc Production	2C	
2.C.7	Other (please specify)	2C	
2.D.1	Lubricant Use	2G	
2.D.2	Paraffin Wax Use	2G	
2.D.3	Solvent Use	3	
2.D.4	Other (please specify)	2G	

2006 Category most disaggregated level (Emissions are calculated at this level.)		1996 Category Second Level (Emissions are reported at this level in NAI table.)	Note
2.E.1	Integrated Circuit or Semiconductor	2F	CHF3 (HF-C23), CHF2CHF2 (HFC-134), CF4, C2F6 and SF6 are reported in the respective columns in Table 2.
2.E.2	TFT Flat Panel Display	2F	
2.E.3	Photovoltaics	2F	
2.E.4	Heat Transfer Fluid	2F	
2.E.5	Other (please specify)	2F	NF3 is NOT included in either Table 1 or Table 2.
2.F.1.a	Refrigeration and Stationary Air Conditioning	2F	
2.F.1.b	Mobile Air Conditioning	2F	Other HFCs are aggregated in terms of Gg-CO2 eq and included in the column "Other (Gg-CO2)" under "HFC" in Table 2.
2.F.2	Foam Blowing Agents	2F	
2.F.3	Fire Protection	2F	
2.F.4	Aerosols	2F	
2.F.5	Solvents	2F	
2.F.6	Other Applications (please specify)	2F	Other PFCs are aggregated in terms of Gg-CO2 eq and included in the column "Other (Gg-CO2)" under "PFC" in Table 2.
2.G.1.a	Manufacture of Electrical Equipment	2F	
2.G.1.b	Use of Electrical Equipment	2F	
2.G.1.c	Disposal of Electrical Equipment	2F	CO2, CH4 and N2O from 2.E.5 are reported in the row "7 - Other (please specify)" in Table 1.
2.G.2.a	Military Applications	2F	
2.G.2.b	Accelerators	2F	
2.G.2.c	Other (please specify)	2F	
2.G.3.a	Medical Applications	3	
2.G.3.b	Propellant for pressure and aerosol products	3	
2.G.3.c	Other (Please specify)	3	
2.G.4	Other (Please specify)	3	For CO2, CH4, N2O
		2F	For HFC, PFC, SF6 (Details are the same for 2F as shown above.)
2.H.1	Pulp and Paper Industry	2D	
2.H.2	Food and Beverages Industry	2D	
2.H.3	Other (please specify)	2G	
3.A.1.a.i	Dairy Cows	4A	
3.A.1.a.ii	Other Cattle	4A	
3.A.1.b	Buffalo	4A	
3.A.1.c	Sheep	4A	
3.A.1.d	Goats	4A	
3.A.1.e	Camels	4A	
3.A.1.f	Horses	4A	
3.A.1.g	Mules and Asses	4A	
3.A.1.h	Swine	4A	
3.A.1.j	Other (please specify)	4A	
3.A.2.a.i	Dairy Cows	4B	
3.A.2.a.ii	Other Cattle	4B	
3.A.2.b	Buffalo	4B	
3.A.2.c	Sheep	4B	
3.A.2.d	Goats	4B	
3.A.2.e	Camels	4B	
3.A.2.f	Horses	4B	
3.A.2.g	Mules and Asses	4B	
3.A.2.h	Swine	4B	
3.A.2.i	Poultry	4B	

2006 Category most disaggregated level (Emissions are calculated at this level.)		1996 Category Second Level (Emissions are reported at this level in NAI table.)	Note
3.A.2.j	Other (please specify)	4B	
3.B.1.a	Forest land Remaining Forest land	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.1.b.i	Cropland converted to Forest Land	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, when the user did NOT choose "This is caused by abandonment of managed land."
		5C	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, when the user chose "This is caused by abandonment of managed land."
		5D	For Soil
3.B.1.b.ii	Grassland converted to Forest Land	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, when the user did NOT choose "This is caused by abandonment of managed land."
		5C	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, when the user chose "This is caused by abandonment of managed land."
		5D	For Soil
3.B.1.b.iii	Wetlands converted to Forest Land	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, when the user did NOT choose "This is caused by abandonment of managed land."
		5C	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, when the user chose "This is caused by abandonment of managed land."
		5D	For Soil
3.B.1.b.iv	Settlements converted to Forest Land	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, when the user did NOT choose "This is caused by abandonment of managed land."
		5C	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, when the user chose "This is caused by abandonment of managed land."
		5D	For Soil

2006 Category most disaggregated level (Emissions are calculated at this level.)		1996 Category Second Level (Emissions are reported at this level in NAI table.)	Note
3.B.1.b.v	Other Land converted to Forest Land	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, when the user did NOT choose "This is caused by abandonment of managed land."
		5C	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, when the user chose "This is caused by abandonment of managed land."
		5D	For Soil
3.B.2.a	Cropland Remaining Cropland	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.2.b.i	Forest Land converted to Cropland	5B	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.2.b.ii	Grassland converted to Cropland	5B	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.2.b.iii	Wetlands converted to Cropland	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.2.b.iv	Settlements converted to Cropland	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.2.b.v	Other Land converted to Cropland	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.3.a	Grassland Remaining Grassland	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.3.b.i	Forest Land converted to Grassland	5B	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.3.b.ii	Cropland converted to Grassland	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.3.b.iii	Wetlands converted to Grassland	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil

2006 Category most disaggregated level (Emissions are calculated at this level.)		1996 Category Second Level (Emissions are reported at this level in NAI table.)	Note
3.B.3.b.iv	Settlements converted to Grassland	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.3.b.v	Other Land converted to Grassland	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.4.a.i	Peatlands remaining peatlands	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.4.a.ii	Flooded land remaining flooded land	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.4.b.i	Land converted for peat extraction	5B	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, for Forest Land converted for peat extraction
		5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, for other than Forest Land converted for peat extraction
		5D	For Soil
3.B.4.b.ii	Land converted to flooded land	5B	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, for Forest Land converted for peat extraction
		5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, for other than Forest Land converted for peat extraction
		5D	For Soil
3.B.4.b.iii	Land converted to other wetlands	5B	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, for Forest Land converted for peat extraction
		5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter, for other than Forest Land converted for peat extraction
		5D	For Soil

2006 Category most disaggregated level (Emissions are calculated at this level.)		1996 Category Second Level (Emissions are reported at this level in NAI table.)	Note
3.B.5.a	Settlements Remaining Settlements	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.5.b.i	Forest Land converted to Settlements	5B	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.5.b.ii	Cropland converted to Settlements	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.5.b.iii	Grassland converted to Settlements	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.5.b.iv	Wetlands converted to Settlements	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.5.b.v	Other land converted to Settlements	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.6.a	Other land Remaining Other land	5A	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.6.b.i	Forest Land converted to Other Land	5B	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.6.b.ii	Cropland converted to Other Land	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.6.b.iii	Grassland converted to Other Land	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.6.b.iv	Wetlands converted to Other Land	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.B.6.b.v	Settlements converted to Other Land	5E	For Above-ground Biomass, Below-ground Biomass, Dead Organic Matter
		5D	For Soil
3.C.1.a	Biomass burning in forest lands	5E	

2006 Category most disaggregated level (Emissions are calculated at this level.)		1996 Category Second Level (Emissions are reported at this level in NAI table.)	Note
3.C.1.b	Biomass burning in croplands	4F	When the user chose "This is caused by agricultural residue burning."
		5B	When the user did not choose "This is caused by agricultural residue burning.", and this is on Forest land converted to Cropland or on Grassland converted to Cropland.
		5E	Otherwise
3.C.1.c	Biomass burning in grasslands	4E	When the user chose "This is caused by prescribed burning of savannas."
		5B	When the user did not choose "This is caused by prescribed burning of savannas.", and this is on Grassland converted to Cropland.
		5E	Otherwise
3.C.1.d	Biomass burning in all other land	5B	For Forest land converted to other land-use category or for Grassland converted to other land-use category.
		5E	Otherwise
3.C.2	Liming	5D	
3.C.3	Urea application	N.A.	The emissions under 3.C.3 (Urea application) is excluded, since they are already reported under 2B of 1996 GLs. See note for category 2.B.1.
3.C.4	Direct N2O Emissions from managed soils	4D	For Cropland & Grassland
		5B	For Forest land converted to non-Forestland, and Grassland converted to non-Grassland
		5E	Otherwise
3.C.5	Indirect N2O Emissions from managed soils	4D	For Cropland & Grassland
		5B	For Forest land converted to non-Forestland, and Grassland converted to non-Grassland
		5E	Otherwise
3.C.6	Indirect N2O Emissions from manure management	4B	
3.C.7	Rice cultivations	4C	
3.C.8	Other (please specify)	5E	
3.D.1	Harvested Wood Products	5E	
3.D.2	Other (please specify)	5E	
4.A	Solid Waste Disposal	6A	
4.A.1	Managed Waste Disposal Sites	6A1	
4.A.2	Unmanaged Waste Disposal Sites	6A2	
4.A.3	Uncategorised Waste Disposal Sites	6A3	

2006 Category most disaggregated level (Emissions are calculated at this level.)		1996 Category Second Level (Emissions are reported at this level in NAI table.)	Note
4.B	Biological Treatment of Solid Waste	6D	
4.C	Incineration and Open Burning of Waste	6C	
4.C.1	Waste Incineration	6C	
4.C.2	Open Burning of Waste	6C	
4.D	Wastewater Treatment and Discharge	6B	
4.D.1	Domestic Wastewater Treatment and Discharge	6B2	
4.D.2	Industrial Wastewater Treatment and Discharge	6B1	
4.E	Other (please specify)	6D	